

Alibaba Cloud Apsara Stack Agility SE

Operations and Maintenance Guide

Version: 2003, Internal: V3.2.0

Issue: 20200618









Legal disclaimer

Alibaba Cloud reminds you to carefully read and fully understand the terms and conditions of this legal disclaimer before you read or use this document. If you have read or used this document, it shall be deemed as your total acceptance of this legal disclaimer.

1. You shall download and obtain this document from the Alibaba Cloud website or other Alibaba Cloud-authorized channels, and use this document for your own legal business activities only. The content of this document is considered confidential information of Alibaba Cloud. You shall strictly abide by the confidentiality obligations. No part of this document shall be disclosed or provided to any third party for use without the prior written consent of Alibaba Cloud.
2. No part of this document shall be excerpted, translated, reproduced, transmitted, or disseminated by any organization, company, or individual in any form or by any means without the prior written consent of Alibaba Cloud.
3. The content of this document may be changed due to product version upgrades, adjustments, or other reasons. Alibaba Cloud reserves the right to modify the content of this document without notice and the updated versions of this document will be occasionally released through Alibaba Cloud-authorized channels. You shall pay attention to the version changes of this document as they occur and download and obtain the most up-to-date version of this document from Alibaba Cloud-authorized channels.
4. This document serves only as a reference guide for your use of Alibaba Cloud products and services. Alibaba Cloud provides the document in the context that Alibaba Cloud products and services are provided on an "as is", "with all faults" and "as available" basis. Alibaba Cloud makes every effort to provide relevant operational guidance based on existing technologies. However, Alibaba Cloud hereby makes a clear statement that it in no way guarantees the accuracy, integrity, applicability, and reliability of the content of this document, either explicitly or implicitly. Alibaba Cloud shall not bear any liability for any errors or financial losses incurred by any organizations, companies, or individuals arising from their download, use, or trust in this document. Alibaba Cloud shall not, under any circumstances, bear responsibility for any indirect, consequential, exemplary, incidental, special, or punitive damages, including lost profits arising from the use or trust in this document, even if Alibaba Cloud has been notified of the possibility of such a loss.

- 5.** By law, all the contents in Alibaba Cloud documents, including but not limited to pictures, architecture design, page layout, and text description, are intellectual property of Alibaba Cloud and/or its affiliates. This intellectual property includes, but is not limited to, trademark rights, patent rights, copyrights, and trade secrets. No part of this document shall be used, modified, reproduced, publicly transmitted, changed, disseminated, distributed, or published without the prior written consent of Alibaba Cloud and/or its affiliates. The names owned by Alibaba Cloud shall not be used, published, or reproduced for marketing, advertising, promotion, or other purposes without the prior written consent of Alibaba Cloud. The names owned by Alibaba Cloud include, but are not limited to, "Alibaba Cloud", "Aliyun", "HiChina", and other brands of Alibaba Cloud and/or its affiliates, which appear separately or in combination, as well as the auxiliary signs and patterns of the preceding brands, or anything similar to the company names, trade names, trademarks, product or service names, domain names, patterns, logos, marks, signs, or special descriptions that third parties identify as Alibaba Cloud and/or its affiliates.
- 6.** Please contact Alibaba Cloud directly if you discover any errors in this document.

Document conventions

Style	Description	Example
	A danger notice indicates a situation that will cause major system changes, faults, physical injuries, and other adverse results.	 Danger: Resetting will result in the loss of user configuration data.
	A warning notice indicates a situation that may cause major system changes, faults, physical injuries, and other adverse results.	 Warning: Restarting will cause business interruption. About 10 minutes are required to restart an instance.
	A caution notice indicates warning information, supplementary instructions, and other content that the user must understand.	 Notice: If the weight is set to 0, the server no longer receives new requests.
	A note indicates supplemental instructions, best practices, tips, and other content.	 Note: You can use Ctrl + A to select all files.
>	Closing angle brackets are used to indicate a multi-level menu cascade.	Click Settings > Network > Set network type .
Bold	Bold formatting is used for buttons, menus, page names, and other UI elements.	Click OK .
Courier font	Courier font is used for commands.	Run the <code>cd /d C:/window</code> command to enter the Windows system folder.
Italic	Italic formatting is used for parameters and variables.	<code>bae log list --instanceid Instance_ID</code>
[] or [a b]	This format is used for an optional value, where only one item can be selected.	<code>ipconfig [-all -t]</code>

Style	Description	Example
{ } or {a b}	This format is used for a required value, where only one item can be selected.	switch {active stand}

Contents

Legal disclaimer.....	I
Document conventions.....	I
1 Apsara Stack Operations overview.....	1
2 Preparations before operations.....	3
2.1 Prepare an operations account.....	3
2.2 Log on to Apsara Stack Operations.....	3
2.3 Web page introduction.....	5
3 System settings.....	6
3.1 Default operations roles.....	6
3.2 System Management.....	6
3.2.1 Department management.....	7
3.2.2 Role management.....	8
3.2.3 Logon policy management.....	9
3.2.4 User management.....	10
3.2.5 Two factor authentication.....	14
3.2.6 Application whitelist.....	17
3.2.7 Server password management.....	18
3.2.8 Operation logs.....	21
4 Monitoring.....	23
4.1 Alarm Monitoring.....	23
4.1.1 Overview.....	23
4.1.2 Alert events.....	26
4.1.3 Alert history.....	28
4.1.4 Alert configuration.....	29
4.1.4.1 Alert contacts.....	29
4.1.4.2 Alert contact groups.....	30
4.1.4.3 Static parameter settings.....	31
4.1.5 Alert overview.....	33
4.1.6 Alert subscription and push.....	34
4.1.7 Alert masking.....	36
4.1.7.1 Add a masking rule.....	36
4.1.7.2 Remove the masking.....	39
4.2 Physical servers.....	40
4.2.1 View the physical server information.....	40
4.2.2 Add a physical server.....	43
4.2.3 Modify a physical server.....	44
4.2.4 Export the physical server information.....	44
4.2.5 Delete a physical server.....	45
4.3 Inventory Management.....	46

4.3.1 View the RDS inventory.....	46
4.3.2 View the OSS inventory.....	46
4.4 Storage Operation Center.....	47
4.4.1 Pangu.....	47
4.4.1.1 Pangu grail.....	47
4.4.1.2 Cluster information.....	49
4.4.1.3 Node information.....	51
4.4.1.4 Pangu operation.....	53
4.4.1.5 Product settings.....	53
4.4.2 miniOSS.....	56
4.4.2.1 Monitoring dashboard.....	56
4.4.2.2 User management.....	60
4.4.2.3 Permission and quota management.....	62
4.4.2.4 Array monitoring.....	64
4.4.2.5 System management.....	64
5 Operations tools.....	66
5.1 NOC.....	66
5.1.1 Network topology.....	66
5.1.2 Resource management.....	67
5.1.2.1 Device management.....	67
5.1.2.1.1 View the network monitoring information.....	67
5.1.2.1.2 View logs.....	70
5.1.2.1.3 Collection settings.....	70
5.1.2.1.3.1 Modify the collection interval.....	70
5.1.2.1.3.2 Add an OOB network segment.....	71
5.1.2.1.3.3 Modify the OOB network segment information.....	72
5.1.2.1.3.4 Delete an OOB network segment.....	73
5.1.2.2 View the instance monitoring information.....	73
5.1.3 Alert management.....	74
5.1.3.1 View and process current alerts.....	74
5.1.3.2 View history alerts.....	74
5.1.3.3 Add a trap.....	75
5.1.3.4 View a trap.....	78
5.2 Task Management.....	79
5.2.1 Overview.....	79
5.2.2 View the task overview.....	79
5.2.3 Create a task.....	80
5.2.4 View the execution status of a task.....	85
5.2.5 Start a task.....	86
5.2.6 Delete a task.....	87
5.2.7 Process tasks to be intervened.....	87
5.2.8 Configure the XDB backup task.....	88
5.3 Apsara Infrastructure Management Framework.....	91
5.3.1 Old version.....	91
5.3.1.1 What is Apsara Infrastructure Management Framework?.....	91

5.3.1.1.1 Overview.....	91
5.3.1.1.2 Basic concepts.....	92
5.3.1.2 Log on to Apsara Infrastructure Management Framework.....	94
5.3.1.3 Web page introduction.....	96
5.3.1.3.1 Introduction on the home page.....	96
5.3.1.3.2 Introduction on the left-side navigation pane.....	99
5.3.1.4 Cluster operations.....	101
5.3.1.4.1 View cluster configurations.....	101
5.3.1.4.2 View the cluster dashboard.....	103
5.3.1.4.3 View the cluster operation and maintenance center.....	107
5.3.1.4.4 View the service final status.....	110
5.3.1.4.5 View operation logs.....	112
5.3.1.5 Service operations.....	113
5.3.1.5.1 View the service list.....	113
5.3.1.5.2 View the service instance dashboard.....	114
5.3.1.5.3 View the server role dashboard.....	116
5.3.1.6 Machine operations.....	119
5.3.1.6.1 View the machine dashboard.....	119
5.3.1.7 Monitoring center.....	122
5.3.1.7.1 Modify an alert rule.....	122
5.3.1.7.2 View the status of a monitoring instance.....	122
5.3.1.7.3 View the alert status.....	122
5.3.1.7.4 View alert rules.....	123
5.3.1.7.5 View the alert history.....	124
5.3.1.8 Tasks and deployment summary.....	125
5.3.1.8.1 View rolling tasks.....	125
5.3.1.8.2 View running tasks.....	127
5.3.1.8.3 View history tasks.....	128
5.3.1.8.4 View the deployment summary.....	128
5.3.1.9 Reports.....	131
5.3.1.9.1 View reports.....	131
5.3.1.9.2 Add a report to favorites.....	132
5.3.1.10 Metadata operations.....	133
5.3.1.10.1 Common parameters.....	133
5.3.1.10.2 Access APIs.....	135
5.3.1.10.3 APIs on the control side.....	136
5.3.1.10.3.1 DescribeInstance.....	137
5.3.1.10.3.2 ListInstance.....	140
5.3.1.10.3.3 CreateInstance.....	141
5.3.1.10.3.4 DeleteInstance.....	142
5.3.1.10.3.5 RestartInstance.....	143
5.3.1.10.3.6 UpgradeInstance.....	144
5.3.1.10.3.7 DescribeTaskProgress.....	144
5.3.1.10.3.8 ChangeLeaderTo.....	146
5.3.1.10.3.9 ModifyInstanceLevel.....	147

5.3.1.10.3.10 DescribeLeader.....	148
5.3.1.10.3.11 RecreateNode.....	149
5.3.1.10.3.12 CreateDatabase.....	150
5.3.1.10.3.13 DeleteDatabase.....	151
5.3.1.10.3.14 DeleteUser.....	151
5.3.1.10.4 APIs on the deployment side.....	152
5.3.1.10.4.1 CheckHealth.....	153
5.3.1.10.4.2 CheckState.....	154
5.3.1.10.4.3 DescribeNodeStatus.....	155
5.3.1.10.4.4 ListNode.....	158
5.3.1.10.4.5 BackupNode.....	159
5.3.1.11 Appendix.....	160
5.3.1.11.1 IP list.....	160
5.3.1.11.2 Project component info report.....	160
5.3.1.11.3 Machine info report.....	161
5.3.1.11.4 Rolling info report.....	163
5.3.1.11.5 Machine RMA approval pending list.....	165
5.3.1.11.6 Registration vars of services.....	166
5.3.1.11.7 Virtual machine mappings.....	166
5.3.1.11.8 Service inspector report.....	167
5.3.1.11.9 Resource application report.....	167
5.3.1.11.10 Statuses of project components.....	168
5.3.1.11.11 Relationship of service dependency.....	170
5.3.1.11.12 Check report of network topology.....	171
5.3.1.11.13 Clone report of machines.....	171
5.3.1.11.14 Auto healing/install approval pending report.....	172
5.3.1.11.15 Machine power on or off statuses of clusters.....	172
5.3.2 New version.....	174
5.3.2.1 What is Apsara Infrastructure Management Framework?.....	174
5.3.2.1.1 Introduction.....	174
5.3.2.1.2 Basic concepts.....	175
5.3.2.2 Log on to Apsara Infrastructure Management Framework.....	177
5.3.2.3 Homepage introduction.....	179
5.3.2.4 Project operations.....	182
5.3.2.5 Cluster operations.....	183
5.3.2.5.1 View the cluster list.....	183
5.3.2.5.2 View the cluster details.....	185
5.3.2.5.3 View operation logs.....	188
5.3.2.6 Service operations.....	188
5.3.2.6.1 View the service list.....	189
5.3.2.6.2 View the server role details.....	189
5.3.2.7 Machine operations.....	191
5.3.2.8 Monitoring center.....	192
5.3.2.8.1 View the monitoring instance status.....	192
5.3.2.8.2 View the alert status.....	193

5.3.2.8.3 View alert rules.....	194
5.3.2.8.4 View the alert history.....	195
5.3.2.9 View tasks.....	196
5.3.2.10 Reports.....	197
5.3.2.10.1 View reports.....	197
5.3.2.10.2 Add a report to favorites.....	199
5.3.2.11 Tools.....	199
5.3.2.11.1 Machine tools.....	199
5.3.2.11.2 IDC shutdown.....	201
5.3.2.11.3 View the clone progress.....	201
5.3.2.12 Metadata operations.....	202
5.3.2.12.1 Common parameters.....	202
5.3.2.12.2 Access APIs.....	204
5.3.2.12.3 APIs on the control side.....	205
5.3.2.12.3.1 DescribeInstance.....	206
5.3.2.12.3.2 ListInstance.....	209
5.3.2.12.3.3 CreateInstance.....	210
5.3.2.12.3.4 DeleteInstance.....	211
5.3.2.12.3.5 RestartInstance.....	212
5.3.2.12.3.6 UpgradeInstance.....	213
5.3.2.12.3.7 DescribeTaskProgress.....	213
5.3.2.12.3.8 ChangeLeaderTo.....	215
5.3.2.12.3.9 ModifyInstanceLevel.....	216
5.3.2.12.3.10 DescribeLeader.....	217
5.3.2.12.3.11 RecreateNode.....	218
5.3.2.12.3.12 CreateDatabase.....	219
5.3.2.12.3.13 DeleteDatabase.....	220
5.3.2.12.3.14 DeleteUser.....	220
5.3.2.12.4 APIs on the deployment side.....	221
5.3.2.12.4.1 CheckHealth.....	222
5.3.2.12.4.2 CheckState.....	223
5.3.2.12.4.3 DescribeNodeStatus.....	224
5.3.2.12.4.4 ListNode.....	227
5.3.2.12.4.5 BackupNode.....	228
5.3.2.13 Appendix.....	228
5.3.2.13.1 Project component info report.....	229
5.3.2.13.2 IP list.....	229
5.3.2.13.3 Machine info report.....	230
5.3.2.13.4 Rolling info report.....	232
5.3.2.13.5 Machine RMA approval pending list.....	234
5.3.2.13.6 Registration vars of services.....	235
5.3.2.13.7 Virtual machine mappings.....	235
5.3.2.13.8 Service inspector report.....	236
5.3.2.13.9 Resource application report.....	236
5.3.2.13.10 Statuses of project components.....	237

5.3.2.13.11 Relationship of service dependency.....	239
5.3.2.13.12 Check report of network topology.....	240
5.3.2.13.13 Clone report of machines.....	240
5.3.2.13.14 Auto healing/install approval pending report.....	241
5.3.2.13.15 Machine power on or off statuses of clusters.....	241
6 Products.....	244
6.1 Product list.....	244
6.2 ISV access configurations.....	245
6.2.1 Configure the ISV access information.....	245
6.2.2 Modify the ISV access information.....	245
6.2.3 Delete the ISV access information.....	246
7 Log configurations.....	247
7.1 What is LogAgentconfig?.....	247
7.2 Log on to the LogAgentconfig console.....	247
7.3 Configure log collection.....	249
8 Log O&M.....	251
8.1 Kibana Log O&M.....	251
8.1.1 Overview of the Kibana log O&M platform.....	251
8.1.2 Log on to the Kibana log O&M platform.....	251
8.1.3 Quick start.....	253
8.1.3.1 Create index patterns.....	253
8.1.3.2 View data in documents.....	256
8.1.3.3 Filter data by using a time filter.....	259
8.1.3.4 Filter data by using column charts.....	260
8.1.3.5 Query data by using KQL.....	261
8.1.4 Explore data.....	262
8.1.4.1 Open a saved search.....	262
8.1.4.2 View statistics for field data.....	263
8.1.4.3 Filter by fields.....	265
8.1.4.4 Configure a refresh interval.....	269
8.1.4.5 Save a search.....	270
8.1.5 Use development tools to retrieve data.....	271
8.1.6 Manage index patterns.....	272
8.1.6.1 Set the default index pattern.....	272
8.1.6.2 Delete index patterns.....	273
8.1.7 Manage indexes.....	273
8.2 Kafka Manager.....	278
8.2.1 What is Kafka Manager?.....	278
8.2.2 Log on to Kafka Manager.....	278
8.2.3 Quick start.....	279
8.2.3.1 Create a Kafka cluster.....	279
8.2.3.2 View topics in a Kafka cluster.....	282
8.2.3.3 View consumers in a Kafka cluster.....	283
8.2.3.4 View brokers in a Kafka cluster.....	284

8.2.4 Kafka clusters.....	285
8.2.4.1 View a Kafka cluster.....	285
8.2.4.2 Disable or enable a Kafka cluster.....	286
8.2.4.3 Delete a Kafka cluster.....	286
8.2.5 Topics.....	286
8.2.5.1 Create a Kafka topic.....	286
8.2.5.2 Generate partition assignments.....	287
8.2.5.3 Add partitions.....	289
8.2.5.4 Run partition assignments.....	292
8.2.5.5 Reassign partitions.....	293
8.2.5.6 Update configurations for a topic.....	294
8.2.5.7 Manually assign partitions.....	298
8.2.5.8 Configure automatic partition assignment.....	299
8.2.5.9 Delete a topic.....	299
9 PaaS operations and maintenance.....	301
9.1 PaaS console.....	301
9.1.1 PaaS console overview.....	301
9.1.2 Log on to the PaaS console.....	301
9.1.3 Platform overview.....	303
9.1.4 Clusters.....	303
9.1.4.1 View the cluster list.....	303
9.1.4.2 Node management.....	304
9.1.4.2.1 Add a tag.....	304
9.1.4.2.2 Add a taint.....	306
9.1.4.2.3 Query nodes by tag.....	307
9.1.4.2.4 Delete a tag.....	308
9.1.4.2.5 Delete a taint.....	309
9.1.5 Product center.....	310
9.1.5.1 Product list.....	310
9.1.5.1.1 View product details.....	310
9.1.5.1.2 View component information.....	311
9.1.5.1.3 View the deployment progress of product components.....	311
9.1.5.1.4 Log on to a web terminal.....	312
9.1.5.1.5 Perform O&M actions.....	313
9.1.5.1.6 View a resource report.....	313
9.1.5.1.7 View service registration variables.....	314
9.1.5.2 Deployment and upgrade.....	315
9.1.6 Task center.....	318
9.1.6.1 Task templates.....	318
9.1.6.1.1 View a task template.....	318
9.1.6.1.2 Run a task.....	319
9.1.6.2 Task instances.....	320
9.1.6.2.1 View task details.....	320
9.1.6.2.2 Suspend a task.....	321
9.1.6.2.3 Resume a task.....	322

9.1.6.2.4 Terminate a task.....	322
9.1.6.2.5 Retry a task.....	323
9.1.6.2.6 Delete a task.....	324
9.1.7 Platform diagnostics.....	324
9.1.7.1 Diagnostic items.....	325
9.1.7.1.1 View a diagnostic item.....	325
9.1.7.1.2 Execute a diagnostic item.....	325
9.1.7.1.3 Delete a diagnostic item.....	326
9.1.7.2 Diagnostic tasks.....	326
9.1.7.2.1 View diagnostic progress.....	326
9.1.7.2.2 View a diagnostic report.....	327
9.1.7.2.3 Download a diagnostic report.....	327
9.1.7.2.4 Terminate a diagnostic task.....	328
9.1.7.2.5 Delete a diagnostic task.....	328
9.1.8 Alerts.....	328
9.1.8.1 Alert rule groups.....	328
9.1.8.1.1 Create an alert rule group.....	328
9.1.8.1.2 Add an alert rule.....	330
9.1.8.1.3 Modify an alert rule.....	332
9.1.8.1.4 Delete an alert rule.....	333
9.1.8.1.5 Delete an alert rule group.....	333
9.1.8.2 Notification channels.....	334
9.1.8.2.1 View notification channel settings.....	334
9.1.8.2.2 Modify notification channel settings.....	334
9.1.8.2.2.1 Modify global settings.....	334
9.1.8.2.2.2 Modify routing settings.....	337
9.1.8.2.2.3 Modify receiver settings.....	341
9.1.8.3 Alert events.....	343
9.1.8.3.1 View aggregated alert events by alert name.....	343
9.1.8.3.2 View aggregated alert events by product name.....	344
9.1.8.3.3 View all alert events.....	345
9.2 Harbor-based image repository console.....	345
9.2.1 Overview.....	345
9.2.2 Preparations.....	346
9.2.2.1 Query the domain name of the Harbor-based image repository.....	346
9.2.2.2 Configure host information.....	347
9.2.3 Log on to the Harbor-based image repository console.....	348
9.2.4 Create users.....	349
9.2.5 Create projects.....	350
9.2.6 Grant project permissions.....	352
9.2.7 Push images.....	353
10 Operations of basic cloud products.....	357
10.1 ApsaraDB for RDS.....	357
10.1.1 Architecture.....	357
10.1.1.1 System architecture.....	357

10.1.1.1.1 Backup system.....	357
10.1.1.1.2 Monitoring system.....	357
10.1.1.1.3 Control system.....	358
10.1.1.1.4 Task scheduling system.....	358
10.1.2 Log on to the Apsara Stack Operations console.....	358
10.1.3 Instance management.....	360
10.1.4 Manage hosts.....	362
10.1.5 Security maintenance.....	363
10.1.5.1 Network security maintenance.....	363
10.1.5.2 Account password maintenance.....	363
11 Apsara Opsapi Management system.....	364
11.1 Apsara Opsapi Management system overview.....	364
11.2 Log on to the Apsara Opsapi Management system.....	365
11.3 API management.....	367
11.3.1 Register APIs.....	367
11.3.2 Modify information about APIs.....	367
11.3.3 Test APIs.....	369
11.3.4 Remove information about APIs.....	370
11.3.5 API design.....	370
11.3.5.1 API designer.....	370
11.3.5.2 Designer nodes.....	371
11.3.5.3 Design an API flow.....	371
11.4 Version management.....	372
11.4.1 Apsara Stack version management.....	372
11.4.1.1 Add information about versions.....	372
11.4.1.2 Select products for an Apsara Stack version.....	373
11.4.1.3 Compare versions.....	374
11.4.1.4 Remove information about Apsara Stack versions.....	376
11.4.2 Product baseline management.....	376
11.4.3 Product management.....	377
11.4.3.1 Add information about products.....	377
11.4.3.2 Add information about product versions.....	378
11.4.3.3 Import information about APIs.....	378
11.4.3.4 Set SDK versions.....	379
11.4.3.5 Modify product names and descriptions.....	379
11.4.3.6 View information about product versions.....	380
11.4.3.7 Modify information about product versions.....	380
11.4.3.8 Remove information about product versions.....	380
11.4.3.9 Remove information about products.....	381
11.4.3.10 Remove information about product APIs.....	381
11.4.4 SDK management.....	382
11.4.4.1 Customize SDKs.....	382
11.4.4.2 Modify SDKs.....	383
11.4.4.3 Delete SDKs.....	384
11.5 Test management.....	384

11.5.1 Test cases.....	384
11.5.1.1 Modify test cases.....	384
11.5.1.2 Run test cases.....	385
11.5.1.3 Delete test cases.....	386
11.5.2 Test sets.....	386
11.5.2.1 Create test sets.....	386
11.5.2.2 Associate test cases.....	386
11.5.2.3 Run test sets.....	387
11.5.2.4 Delete test sets.....	387
11.5.3 View execution history of test cases.....	388
11.6 System management.....	388
11.6.1 Metadatabase management.....	388
11.6.1.1 View information about added metadatabases.....	388
11.6.1.2 View connection information about metadatabases.....	390
11.6.1.3 Remove information about metadatabases.....	390
11.6.2 Server management.....	391
11.6.2.1 View information about added servers.....	391
11.6.2.2 Remove server information.....	392
11.6.3 Audit APIs.....	393
11.6.4 View logs.....	393
12 Appendix.....	395
12.1 Operation Access Manager (OAM).....	395
12.1.1 OAM introduction.....	395
12.1.2 Instructions.....	396
12.1.3 Quick start.....	397
12.1.3.1 Log on to OAM.....	397
12.1.3.2 Create a group.....	399
12.1.3.3 Add group members.....	399
12.1.3.4 Add group roles.....	400
12.1.3.5 Create a role.....	400
12.1.3.6 Add inherited roles to a role.....	401
12.1.3.7 Add resources to a role.....	401
12.1.3.8 Add authorized users to a role.....	402
12.1.4 Manage groups.....	403
12.1.4.1 Modify the group information.....	403
12.1.4.2 View group role details.....	404
12.1.4.3 Delete a group.....	404
12.1.4.4 View authorized groups.....	405
12.1.5 Manage roles.....	405
12.1.5.1 Search for roles.....	405
12.1.5.2 Modify the role information.....	405
12.1.5.3 View the role inheritance tree.....	406
12.1.5.4 Transfer roles.....	406
12.1.5.5 Delete a role.....	406
12.1.5.6 View authorized roles.....	407

12.1.5.7 View all roles.....	407
12.1.6 Search for resources.....	407
12.1.7 View the personal information.....	408
12.1.8 Appendix.....	409
12.1.8.1 Default roles and their functions.....	409
12.1.8.1.1 Default role of OAM.....	409
12.1.8.1.2 Default roles of Apsara Infrastructure Management Framework.....	409
12.1.8.1.3 Default role of Tianjimon.....	411
12.1.8.2 Permission lists of operations platforms.....	412
12.1.8.2.1 Permission list of Apsara Infrastructure Management Framework...	412
12.1.8.2.2 Permission list of Tianjimon.....	421

1 Apsara Stack Operations overview

Apsara Stack Operations (ASO) is an operations management system developed for the Apsara Stack operations management personnel, such as field operations engineers, operations engineers on the user side, and operations management engineers, operations security personnel, and audit personnel of the cloud platform. ASO allows the operations engineers to master the operating conditions of the system in time and perform Operations & Maintenance (O&M) operations.

ASO has the following main functions:

- Alarm Monitoring

The Alarm Monitoring module allows operations engineers to quickly know the information of alerts generated by the system, locate the problems based on the alert information, track the problem processing, and configure the alerts.

- Resource Management

The Resource Management module monitors and manages hardware devices in the data center. You can monitor and manage the overall status information, monitoring metrics, alert delivery status, and port traffic of physical servers, physical switches, and network security devices.

- Inventory Management

The Inventory Management module allows you to view the current usage and inventory of various product resources, and manage resources in the system effectively.

- Products

The Products module allows you to click operations and maintenance services of other products on the cloud platform and ISV access configurations to go to the corresponding page.

- NOC

Network Operation Center (NOC) provides the operations capabilities such as the visualization of network-wide monitoring, automated implementation, automated fault location, and network traffic analysis, which enhances the operations efficiency of network operations engineers, reduces the operations risk, and greatly improves the quality of Apsara Stack network services.

- Storage Operation Center

The Storage Operation Center module contains the pangu section and miniOSS section.

- Task Management

The Task Management module allows you to perform O&M operations in ASO, without using command lines.

- System Management

The System Management module includes the user management, two-factor authentication, role management, department management, logon policy management, and operation logs. As the module for centralized management of accounts, roles, and permissions, System Management supports the Single Sign-On (SSO) function of ASO. After logging on to ASO, you can perform O&M operations on all components of the cloud platform or be redirected to the operations and maintenance page without providing the username or password.

2 Preparations before operations

2.1 Prepare an operations account

Before performing Operations & Maintenance (O&M) operations in Apsara Stack Operations (ASO), make sure that you obtain an operations account with corresponding permissions from the administrator.

Create an operations account and grant permissions to the account as follows:

1. Log on to ASO as a system administrator.
2. Create a role to be granted. For more information, see [Role management](#).
3. Create an operations account and grant the role to the account. For more information, see [User management](#).

**Note:**

To divide permissions of the operations role at a finer granularity, the administrator can create a basic role according to **Appendix > Operation Access Manager (OAM)**, grant permissions to the role, and then grant the role to the corresponding operations account.

2.2 Log on to Apsara Stack Operations

This topic describes how to log on to Apsara Stack Operations (ASO) as users, such as operations engineers.


Prerequisites

- ASO access address in the format of `http://region-id.aso.intranet-domain-id.com`.
- Google Chrome browser (recommended).

Procedure

1. Open the browser.

2. Enter the ASO access address `http://region-id.aso.intranet-domain-id.com` in the address bar and then press Enter.

A screenshot of the ASO Log On interface. It features a dark blue background with the title 'Log On' in white. Below the title, there are two input fields: the first is labeled 'Enter a user name' with a user icon, and the second is labeled 'Enter the password' with a lock icon. At the bottom, there is a prominent blue button labeled 'Log On' in white text.

Note:

You can select the language from the drop-down list in the upper-right corner to change the language of ASO.

3. Enter the correct username and password.



Note:

Obtain the username and password used to log on to ASO from the deployment personnel or the administrator.


- The system has three default users:
 - Security officer: manages other users or roles.
 - Auditor officer: views audit logs.
 - System administrator: used for other functions except those of the security officer and auditor officer.
- You must modify the password of your username as instructed when you log on to ASO for the first time. To improve security, the password must be 10-20 characters long and can contain English uppercase/lowercase letters (A-Z or a-z), numbers (0-9), and special characters, such as exclamation points (!), at signs (@), number signs (#), dollar signs (\$), and percent signs (%), which meets the minimum complexity requirements.

4. Click **Log On** to log on to ASO.

2.3 Web page introduction

After you log on to Apsara Stack Operations (ASO), the Alarm Monitoring page appears.

This topic allows you to get a general understanding of the basic operations and functions of the ASO page.



The description of each area is as follows.

Area		Description
1	Help center	In the Help Center, you can view the alarm knowledge base and upload other documents in the format of html related to operations.
2	Language switching	Select the language from the drop-down list to change the language of ASO.
3	Information of the current logon user	Click this drop-down list to view the information of the current user, modify the password, and complete the logo settings and logon settings.
4	Expand icon	Move the pointer over this icon to expand the left-side navigation pane.
5	Left-side navigation pane	Click to select a specific Operations & Maintenance (O &M) operation.
6	Operating area	The information display area and operating area.

3 System settings

3.1 Default operations roles

This topic describes the default roles of Apsara Stack Operations (ASO) and their responsibilities.

For quick management, the following roles are preset in ASO: OAM super administrator, system administrator, security officer, auditor officer, and multi-cloud configuration administrator. For more information about these roles and their responsibilities, see the following table.

Role	Responsibility
OAM super administrator	The administrator of Operation Access Manager (OAM), with the root permissions of the system.
System administrator	Manages platform nodes, physical devices, and virtual resources, backs up, restores, and migrates product data, and searches for and backs up system logs.
Security officer	Manages permissions, security policies, and network security, and reviews and analyzes security logs and activities of auditor officers.
Auditor officer	Audits, tracks, and analyzes activities of the system administrator and the security officer.
Multi-cloud configuration administrator	Manages multi-cloud operations, and adds, deletes, and modifies multi-cloud configurations.

3.2 System Management

System Management centrally manages the departments, roles, and users involved in Apsara Stack Operations (ASO), making it easy to grant different resource access permissions to different users. As the core module for centralized permission management, the user center integrates the functions such as department management, role management, logon policy management, and user management.

3.2.1 Department management

Department management allows you to create, modify, delete, and search for departments.

Context

After Apsara Stack Operations (ASO) is deployed, a root department is generated by default. You can create other departments under the root department. Departments are displayed in a hierarchy and you can create sub-departments under each level of departments.

A department created under the root department is a level-1 department and a department created under a level-1 department is a level-2 department. In ASO, sub-departments of a department are departments of all levels under the department. Departments reflect the tree structure of an enterprise or business unit. Each user can only belong to one department.

Procedure

1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **System Management > Departments**.
3. On the Department Management page, you can:

- Add a department

Click **Add Department** in the upper-left corner. In the displayed **Add Department** dialog box, enter the **Department Name** and then click **OK**. Then, you can view the created department under your selected catalog.

- Modify a department

Select the department to be modified in the catalog tree and click **Modify Department** at the top of the page. In the displayed **Modify Department** dialog box, enter the **Department Name** and click **OK**.

- Delete a department



Notice:

Before deleting a department, make sure that no user exists in the department. Otherwise, the department cannot be deleted.

Select the department to be deleted in the catalog tree and click **Delete Department** at the top of the page. Click **OK** in the displayed dialog box.

3.2.2 Role management


You can add custom roles in Apsara Stack Operations (ASO) to better allocate permissions to users.

Context

A role is a collection of access permissions. When creating users, you must assign roles to users to meet their access control requirements on the system. Roles are classified into basic roles and user-created roles. The basic roles, also known as atomic roles, are preset by the Operation Access Manager (OAM) system and cannot be modified or deleted by users. The user-created roles can be modified and deleted.

Procedure

1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **System Management** > **Roles**.



Role	Role Description	Permission Details	Actions
		Permission Details	Modify Delete
		Permission Details	Modify Delete
		Permission Details	Modify Delete

3. On the Role Management page, you can:

- Search for roles



Note:

To search for roles in ASO, you must have the ASO security officer role or system administrator role.

In the upper-left corner, enter a role name in the **Role** field and then click **Search** to view the role information in the list.

- Add a role



Note:

To add a role in ASO, you must have the ASO security officer role.

Click **Add** at the top of the page. In the displayed **Add** dialog box, enter the **Role Name** and **Role Description**, select the **Base Role**, and then click **OK**.

- Modify a role



Note:

To modify a role in ASO, you must have the ASO security officer role.

Find the role to be modified, and then click **Modify** in the **Actions** column. In the displayed **Modify Role** dialog box, modify the information and then click **OK**.

- Delete a role

Find the role to be deleted, and then click **Delete** in the **Actions** column. Click **OK** in the displayed dialog box.

3.2.3 Logon policy management

The administrator can configure the logon policies to control the logon time and logon addresses of users.

Context

The system has a default policy as the initial configuration. You can configure the logon policies as required to better control the read and write permissions of users and improve the system security.

Procedure

1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **System Management** > **Logon Policies**.

Logon Policy Management				
<div> <div>Policy Name</div> <div> <input type="text" value="Enter a policy name"/> <input type="button" value="Search"/> <input type="button" value="Add Policy"/> </div> </div>				
Policy Name	Start time	End time	Prohibition Logon IP Addresses	Actions
default_rule	Sep 27, 2019, 22:42:38	Sep 27, 2024, 22:42:38	0.0.0.0/0	Modify Delete

3. On the Logon Policy Management page, you can:

- Search for policies

In the upper-left corner, enter a policy name in the **Policy Name** field and then click **Search** to view the policy information in the list.

- Add a policy

Click **Add Policy**. In the displayed dialog box, configure the **Policy Name**, **Start time**, **End time**, and **IP addresses prohibited for logon**. Then, click **OK**.

- Modify a policy

Find the policy to be modified, and then click **Modify** in the **Actions** column. In the displayed **Update Policy** dialog box, modify the information and then click **OK**.

- Delete a policy

Find the policy to be deleted, and then click **Delete** in the **Actions** column. Click **OK** in the displayed dialog box.

3.2.4 User management

The administrator can create users and assign roles to users to meet their access control requirements on the system.

Prerequisites

Before you create a user, make sure that:

- A department is created. For more information, see [Department management](#).
- A custom role is created, if required. For more information, see [Role management](#).

Context

User management provides different permissions for different users. During the system initialization, the system creates three default users: asosysadmin, asosecurity, and asoauditor. The default users are respectively bound to the following default roles: system administrator, security officer, and auditor officer. The permissions of these three roles are as follows:

- The system administrator can view, modify, delete, and add the information in Alarm Monitoring, Network Operation Center (NOC), Storage Operation Center, and Task Management, and view the users, roles, departments, logon policies, and other modules in System Management.

- The security officer can view, modify, delete, and add the users, roles, departments, and logon policies in System Management.
- The security auditor can read and write Apsara Stack Operations (ASO) system logs.

Procedure

1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **System Management** > **Users**. Click the **Users** tab.
3. On the Users tab, you can:
 - Search for users

**Note:**

To search for users in ASO, you must have the security officer role or system administrator role.

In the upper-left corner, configure the **User Name**, **Role**, and **Department**, and then click **Search** to view the user information in the list.

- Add a user

**Note:**

To add a user in ASO, you must have the ASO security officer role.

Click **Add** at the top of the page. In the displayed **Add User** dialog box, configure the information, such as **User Name** and **Password**, and then click **OK** to add the user.

The added user is displayed in the user list. The **Primary Key Value** of the user is used to call the application API. In other words, the primary key value is used for authentication if other applications need to call the applications in ASO.

- Modify a user

**Note:**

To modify a user in ASO, you must have the ASO security officer role.

Find the user to be modified, and then click **Modify** in the **Actions** column. In the displayed **Modify User** dialog box, modify the information and then click **OK**.

- Delete a user

Find the user to be deleted, and then click **Delete** in the **Actions** column. Click **OK** in the displayed dialog box.



Note:


Deleted users are in the recycle bin. To restore a deleted user, click the **Recycled** tab. Find the user to be restored, click **Cleared** in the **Actions** column, and then click **OK** in the displayed dialog box.

- Bind a logon policy

Select a user in the user list. Click **Bind Logon Policy** to bind a logon policy to the user.

- View personal information of the current user


In the upper-right corner, click the down-arrow button and then select **Personal Information**. The appeared **Personal Information** dialog box displays the personal information of the current user.



- Add a custom logo

In the upper-right corner, click the down-arrow button next to the logon username and then select **Logo Settings**. In the displayed **Custom Settings** dialog box, click


to upload the custom system logo image and system name image and then click **Upload**.



- Logon settings

In the upper-right corner, click the down-arrow button next to the logon username and then select **Logon Settings**. In the displayed **Logon Settings** dialog box,

configure the logon timeout, multiple-terminal logon settings, maximum allowed password retries, account validity, and logon policy. Then, click **Save**.



The screenshot shows a 'Logon Settings' dialog box with a dark blue background and a close button (X) in the top right corner. The settings are organized into sections:

- Logon Timeout (Minutes)**: A numeric input field set to '180' with '+' and '-' buttons to its right, and a 'Restore Default' button below it.
- Multiple-Terminal Logon Settings**: Two radio button options. The first is 'Multiple-Terminal Logon Allowed' (selected with a blue dot) and the second is 'Forbid Multi-Logon in ASO' (unselected). Below these is the text 'Forbid Multi-Logon in O&M'.
- Maximum Allowed Password Retries**: A numeric input field set to '10' with '+' and '-' buttons to its right, and a 'Restore Default' button below it.
- Account Validity (Days)**: A numeric input field set to '30' with '+' and '-' buttons to its right, and a 'Restore Default' button below it.

Below the 'Maximum Allowed Password Retries' section, there is a warning message: 'If you fail to enter the correct password within the specified retry attempts, your account will be locked. Use the administrator account to unlock the account.'

Below the 'Account Validity (Days)' section, there is another warning message: 'Your account has expired. Use the administrator account to unlock your account.'

At the bottom right, there are two buttons: a blue 'Save' button and a white 'Cancel' button with a blue border.

3.2.5 Two factor authentication

To improve the security of user logon, you can configure the two-factor authentication for users.

Context

Currently, Apsara Stack Operations (ASO) supports three authentication methods. Select one method to configure the authentication:

- Google two-factor authentication

This authentication method uses the password and mobile phone to provide double protection for accounts. You can obtain the logon key after configuring users in ASO,

and then enter the key in the Google authenticator app of your mobile phone. The app dynamically generates a verification code based on the time and key for logon.

- USB key authentication

Install the drive and browser controls (currently, only Windows + IE 11 environment is supported) according to the third-party manufacturer instructions if you select this authentication method. The third-party manufacturer provides the USB key hardware and the service that the backend authenticates and verifies the certificates. The USB key hardware includes the serial number and certificate information. Before the authentication, bind the serial number with a user account, configure the authentication server provided by the third-party manufacturer, and enable the USB key authentication for the user when you configure the authentication method in ASO.

Upon logon, if the account enables the USB key authentication, the ASO frontend calls the browser controls, reads the certificate in the USB key, obtains the random code from the backend, encrypts the information, and sends the information to the backend. The backend calls the authentication server to parse the encrypted strings, verifies the certificate and serial number, and then completes the other logon processes if the verification is passed.

- PKI authentication

Enable the ASO HTTPS mutual authentication and change the certificate provided by the user if you select this authentication method. The third-party manufacturer makes the certificate and provides the service that the backend verifies the certificate. After the mutual HTTPS authentication is enabled, the request carries the client certificate upon logon to send the certificate to the backend, and the backend calls the parsing and verification service of the third-party manufacturer to verify the certificate. The certificate includes the name and ID card number of a user. Therefore, bind the name and ID card number with a user account when you configure the authentication method in ASO.

Both USB key authentication and PKI authentication depend on the authentication server provided by the third-party manufacturer to verify the encrypted information or certificate provided upon logon. Therefore, add the authentication server configurations if you select these two authentication methods.

Google two-factor authentication is implemented based on public algorithms. Therefore, no third-party authentication service is required and you are not required to configure the authentication server.

Procedure

1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **System Management** > **Two Factor Authentication**.
3. On the Two Factor Authentication page, you can:
 - Google two-factor authentication
 - a. Select **Google Two-Factor Authentication** as the **Current Authentication Method**.
 - b. Click **Add User** in the upper-right corner. The added user is displayed in the user list.
 - c. Find the user that you are about to enable the Google two-factor authentication, and then click **Create Key** in the **Actions** column. After the key is created, you can click **Show Key** in the Actions column to display the key in plain text.
 - d. Enter the key in the Google authenticator app of your mobile phone. The app dynamically generates a verification code based on the time and key for logon. With the two-factor authentication enabled, you are required to enter the verification code on your app when logging on to the system.

**Note:**

Google two-factor authentication app and server generate the verification code based on the public algorithms of time and keys, and can work offline without connecting to the Internet or Google server. Therefore, keep your key confidential.

- e. To disable the two-factor authentication, click **Delete Key** in the **Actions** column.
- USB key authentication
 - a. Select **USB Key Authentication** as the **Current Authentication Method**.
 - b. In the **Authentication Server Configuration** section, click **Add Server**. In the displayed dialog box, enter the **IP Address** and **Port** of the server, and then

click **OK**. The added server is displayed in the server list. Click **Test** to test the connectivity of the authentication server.

- c. In the **User List** section, click **Add User**. The added user is displayed in the user list.
- d. Find the user that you are about to enable the USB key authentication, and then click **Bind Serial Number** in the **Actions** column. In the displayed dialog box, enter the serial number to bind the user account with this serial number.



Note:

When adding an authentication in ASO, ASO calls the browser controls to automatically enter the serial number. If the serial number fails to be entered, you must enter it manually. The serial number of USB key authentication is written in the USB key hardware. Therefore, you must insert the USB key, install the drive and browser controls, and then read the serial number by calling the browser controls.

- e. Then, click **Enable Authentication** in the **Actions** column.
- PKI authentication
 - a. Select **PKI Authentication** as the **Current Authentication Method**.
 - b. In the **Authentication Server Configuration** section, click **Add Server**. In the displayed dialog box, enter the **IP Address** and **Port** of the server, and then click **OK**. The added server is displayed in the server list. Click **Test** to test the connectivity of the authentication server.
 - c. In the **User List** section, click **Add User**. Enter the **Username**, **Full Name**, and **ID Card Number**, and then click **OK**. The added user is displayed in the user list.
 - d. Find the user that you are about to enable the PKI authentication, and then click **Bind** in the **Actions** column. Enter the full name and ID card number of the user to bind the user account with the name and ID card number.
 - e. Then, click **Enable Authentication** in the **Actions** column.
- No authentication

Select **No Authentication** as the **Current Authentication Method**. Then, the two-factor authentication is disabled. All the two-factor authentication methods become invalid.

3.2.6 Application whitelist

The system administrator can add, modify, or delete an application whitelist.

Context


The application whitelist permissions consist of read-only and read/write. The configured value is the logon user permission. With the whitelist function enabled, the application can be accessed by all users who have successfully logged on.

The application whitelist is managed by the system administrator. You can access this page after logging on as a system administrator.

When adding a whitelist, enter the product name and service name. The current product name is **ASO**, and the service name is the name of the backend service registered in ASO. The whitelist takes effect only if the configurations are correct.

Procedure

1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **System Management** > **Application Whitelist**.



3. On the Application Whitelist page, you can:

- Add a whitelist

In the upper-right corner, click **Add to Whitelist**. In the displayed **Add to Whitelist** dialog box, select the service and permission, and then click **OK**.

- Modify the permission

In the **Permission** drop-down list, modify the permission of the service to **Read/Write** or **Read-only**.

- Delete a whitelist

Find the whitelist to be deleted, and then click **Delete** in the **Actions** column. Click **OK** in the displayed dialog box.

3.2.7 Server password management

The Server Password module allows you to configure and manage server passwords and search for history passwords in the Apsara Stack environment.

Context

Server password management allows you to manage passwords of all the servers in the Apsara Stack environment.

The Server Password module has the following functions:

- Supports viewing the information of all servers in the Apsara Stack environment.
- Supports searching for server passwords by product, hostname, or IP address.
- Supports configuring the password expiration period and password length.
- Supports manually updating the passwords of one or more servers at a time.
- Supports viewing the history of server password updates.

Procedure

1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **System Management** > **Server Password**.

The **Password Management** tab displays the passwords of all the servers in the Apsara Stack environment.

Password Management History Password Configuration							
Product		Hostname		IP			
Select a product		Select a hostname		Please enter IP		Search	
						Batch Update	
						Configuration	
<input type="checkbox"/>	Role	Product	Hostname	IP	Password	Update Time	Actions
<input type="checkbox"/>	ROOT	tianji	a56b08201.cloud.b10.amtest27		*****	Show Sep 27, 2019, 22:42:38	Update Password
<input type="checkbox"/>	ROOT	tianji	a56b08103.cloud.b09.amtest27		*****	Show Sep 27, 2019, 22:42:38	Update Password
<input type="checkbox"/>	ROOT	tianji	a56b08108.cloud.b09.amtest27		*****	Show Sep 27, 2019, 22:42:38	Update Password
<input type="checkbox"/>	ROOT	oss	a56b08000.cloud.b08.amtest27		*****	Show Sep 27, 2019, 22:42:38	Update Password

3. On this tab, you can:

- Search for servers

On the **Password Management** tab, configure the product, hostname, or IP address, and then click **Search** to search for specific servers.

- Show passwords

a. On the **Password Management** tab, find a server.

b. Click **Show** in the **Password** column, and then the system displays the host password in plain text, which turns into cipher text after 10 seconds. Alternatively, directly click **Hide** to display the cipher text.

- Update passwords

a. On the **Password Management** tab, find a server.

b. Click **Update Password** in the **Actions** column.

c. In the displayed **Update Password** dialog box, enter the **Password** and **Confirm Password**, and then click **OK**.

Then, the server password is updated.

- Update multiple passwords at a time

a. On the **Password Management** tab, select multiple servers.

b. Click **Batch Update**.

c. Enter the **Password** and **Confirm Password**, and then click **OK**.

Then, the passwords of the selected servers are updated.

- Configure the password expiration period

a. On the **Password Management** tab, select one or more servers.

b. Click **Configuration**.

c. In the displayed **Configuration Item** dialog box, enter the **Password Expiration Period** and select the **Unit**, and then click **OK**.

Server passwords are updated immediately after the configuration and will be updated again after an expiration period.

- View the history of server password updates

Click the **History Password** tab. Configure the history product, history hostname, or history IP address and then click **Search** to view the history of server password updates in the search results.

- Show history passwords of servers
 - a. On the **History Password** tab, find a server.
 - b. Click **Show** in the **Password** column, and then the system displays the host password in plain text, which turns into cipher text after 10 seconds. Alternatively, directly click **Hide** to display the cipher text.
- View and modify the password configuration policy

Click the **Configuration** tab. View the metadata, including the initial password, password length, and retry times, of server password management. Where,

- The initial password is the one when server password management is deployed in the Apsara Stack environment. This parameter is important, which is used to update the password of a server in the Apsara Stack environment.
- The password length is the length of passwords automatically updated by the system.
- Retry times is the number of retries when the password fails to be updated.

To modify the configurations, click **Modify Configurations** in the **Actions** column. In the displayed dialog box, enter the **Initial Password**, **Password Length**, and **Retry Times**, and then click **OK**.

3.2.8 Operation logs

You can view logs to know the usage of all resources and the operating conditions of all function modules on the platform in real time.

Context

The Operation Logs module allows you to view all the records of backend API calls, including audit operations. The auditor can filter logs by username and time period, view call details, and export the logs.

Procedure

1. [Log on to Apsara Stack Operations](#).

2. In the left-side navigation pane, choose **System Management** > **Operation Logs**.

Log Management

User Name: Time Period: -

<input type="checkbox"/>	Time	Region	User Name	Department	Actions	Details	Operation State
<input type="checkbox"/>	Nov 30, 2019, 17:36:22	cn-xxxxx	xxxxx	root-dept	GET /asoplat-access/permission/hi-story		Successful
<input checked="" type="checkbox"/>	Nov 30, 2019, 17:36:22	cn-xxxxx	xxxxx	root-dept	GET /asoplat-access/permission/pr-oduct		Successful
<input checked="" type="checkbox"/>	Nov 30, 2019, 17:36:22	cn-xxxxx	xxxxx	root-dept	GET /asoplat-access/permission/hi-story/Product		Successful
<input type="checkbox"/>	Nov 30, 2019, 17:36:22	cn-xxxxx	xxxxx	root-dept	GET /asoplat-access/permission/hi-story/Host/Name		Successful

3. On the Log Management page, you can:


- Search for logs

In the upper-left corner, configure the **User Name** and **Time Period**, and then click **Search** to view the log information in the list.

- Delete logs

Select one or more logs to be deleted. Click **Delete** and then click **OK** in the displayed dialog box.

- Export logs

Click  to export the logs of the current page.

4 Monitoring

4.1 Alarm Monitoring

The Alarm Monitoring module allows operations engineers to quickly know the information of alerts generated by the system, locate the problems based on the alert information, track the problem processing, and configure the alerts.


4.1.1 Overview

The Alarm Monitoring module allows you to view the overview information of alerts.

Procedure

1. Log on to Apsara Stack Operations.

By default, the overview page of the Alarm Monitoring module appears after you log on to Apsara Stack Operations (ASO).



2. Then, you can:

- View the total number of alerts and the number of recovered alerts in the basic, critical, important, and minor monitoring metrics, and custom filters.



Note:


Click a monitoring metric or custom filter to go to the corresponding **Alert Events** page.

- Search for alerts

Enter a keyword, such as cluster, product, service, severity, status, and monitoring metric name, in the search box at the top of the page and then click **Search** to search for the corresponding alert event.

- Add a custom filter

Click the  icon. Complete the configurations on the displayed page.




For more information about the configurations, see the following table.

Configuration	Description
Name	The filter name to be displayed on the Alarm Monitoring page.

Configuration	Description
Conditions	<p>Configure the following filter conditions.</p> <ul style="list-style-type: none"> - Service: The service to which the alerts to be filtered belong. - Product: The product to which the alerts to be filtered belong. - Severity: The severity to which the alerts to be filtered belong. <p>The alert severity has the following six levels:</p> <ul style="list-style-type: none"> ■ P0: indicates the cleared alerts, corresponding to alerts whose Alert Level is Restored in Monitoring > Alert History of Apsara Infrastructure Management Framework. ■ P1: indicates the critical alerts, corresponding to alerts whose Alert Level is P1 in Monitoring > Alert History of Apsara Infrastructure Management Framework. ■ P2: indicates the major alerts, corresponding to alerts whose Alert Level is P2 in Monitoring > Alert History of Apsara Infrastructure Management Framework. ■ P3: indicates the minor alerts, corresponding to alerts whose Alert Level is P3 in Monitoring > Alert History of Apsara Infrastructure Management Framework. ■ P4: indicates the remind alerts, corresponding to alerts whose Alert Level is P4 in Monitoring > Alert History of Apsara Infrastructure Management Framework. ■ P5: indicates the system alerts, corresponding to alerts whose Alert Level is P5 in Monitoring > Alert History of Apsara Infrastructure Management Framework. <ul style="list-style-type: none"> - Status: The current status of the alerts to be filtered. - Monitoring Metric Type: The monitoring metric type to which the alerts to be filtered belong. <ul style="list-style-type: none"> ■ Basic ■ Critical ■ Important ■ Minor - Enter the search content: Enter the information of the alerts to be filtered. - Select the start date and end date of the alerts to be filtered .

After adding a custom filter, you can view the overview information that meets the filter conditions in **Alarm Monitoring**.

- Modify a custom filter

After adding a custom filter, you can click the  icon as required to modify the filter conditions and obtain the new filter results.

- Delete a custom filter


After adding a custom filter, you can click the  icon as required to delete it if it is no longer in use.

4.1.2 Alert events

The Alert Events module displays the information of all alerts generated by the system on different tabs. The alert information is aggregated by monitoring item or product name. You can search for alerts based on filter conditions, such as monitoring metric type, product, service, severity, status, and time range when the alert is triggered, and then perform Operation & Maintenance (O&M) operations on the alerts.

Procedure

1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **Alarm Monitoring** > **Alert Events**.



Monitoring Metric	Monitoring Type	Alert Details	Alerts	P1	P2	P3	P4	P5
tanj_ping_monitor	Event	tanj_ping_monitor	6	6	0	0	0	11
tanj_postcheck_monitor	Event	tanj_postcheck_monitor	4	4	0	0	0	27
tanj_project_monitor	Event	tanj_project_monitor	0	0	0	0	0	150

3. Click the **Hardware & System, Base Modules, Monitoring & Management, Cloud Product**, or **Timeout Alert** tab and then you can:

- Search for alerts

At the top of the page, you can search for alerts by **Monitoring Metric Type, Product, Service, Severity, Status, Start Date, End Date**, and search content.

- View alert sources

a. If the alert information is aggregated by **Product Name** on this page, click + at the left of the product name to display the monitoring metrics. If the alert information is aggregated by **Monitoring Item** on this page, skip this step.

b. Find the monitoring metric and severity to which the alerts you are about to view belong, and then click the number in the specific severity column.

c. Move the pointer over the alert source information in blue in the **Alert Source** column to view the alert source details.

- View alert details

a. If the alert information is aggregated by **Product Name** on this page, click + at the left of the product name to display the monitoring metrics. If the alert information is aggregated by **Monitoring Item** on this page, skip this step.

b. Find the monitoring metric and severity to which the alerts you are about to view belong, and then click the number in the specific severity column.

c. Click the value in blue in the **Alert Details** column. On the displayed **Alert Details** page, you can view the alert information, such as the summary, reference, scope, and resolution.

- View the original alert information of an alert

a. If the alert information is aggregated by **Product Name** on this page, click + at the left of the product name to display the monitoring metrics. If the alert information is aggregated by **Monitoring Item** on this page, skip this step.

b. Find the monitoring metric and severity to which the alert you are about to view belongs, and then click the number in the specific severity column.

c. Click the number in blue in the **Alerts** column. The **Alerts** page appears.

d. Click **Details** in the **Alert Information** column to view the original alert information.

- Process an alert

Find the monitoring metric and severity to which the alert you are about to process belongs, and then click the number in the specific severity column.


**Note:**

If the alert information is aggregated by **Product Name** on this page, click + at the left of the product name to display the monitoring metrics.

- If an alert is being processed by operations engineers, click **Actions** > **Process** in the **Actions** column to set the alert status to **In process**.
- If the processing of an alert is finished, click **Actions** > **Processed** in the **Actions** column to set the alert status to **Processed**.
- To view the whole processing flow of an alert, click **Actions** > **Alert Tracing** in the **Actions** column.
- View the recent monitoring data

Click **Actions** > **Exploration** in the **Actions** column at the right of an alert to view the trend chart of a recent monitoring metric of a product.

- Export a report

Click  at the top of the page to export the alert list.

4.1.3 Alert history

The Alert History page displays all the alerts generated by the system and the corresponding information in chronological order.

Procedure


1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **Alarm Monitoring** > **Alert History**.

3. On the Alert History page, you can:

- Search for alerts

At the top of the page, you can search for alerts by **Monitoring Metric Type, Product, Service, Severity, Status, Start Date, End Date**, and search content.

- Export a list of alerts

Click  at the top of the page to export a list of history alerts.

- View alert sources

Move the pointer over an alert source name in blue in the **Alert Source** column to view the alert source details.

- View alert details

Click an alert name in blue in the **Alert Details** column. On the displayed **Alert Details** page, you can view the alert information, such as the summary, reference, scope, and resolution.

- View the original alert information

Click **Details** in the **Alert Information** column to view the original information of the alert.

4.1.4 Alert configuration

The Alert Configuration module provides you with three functions: contacts, contact groups, and static parameter settings.

4.1.4.1 Alert contacts

You can search for, add, modify, or delete an alert contact based on business needs.

Procedure

1. [Log on to Apsara Stack Operations.](#)
2. In the left-side navigation pane, choose **Alarm Monitoring > Alert Configuration**. You are on the **Contacts** tab by default.

Contacts Contact Groups Static Parameter Settings							
Product	Name	Phone	Search		Add		
Product	Role	Name	Phone	DingTalk	Email	Duty Hours	Actions
aso	Developer	Jack	13012345678		jack@example.com	Dec 1, 2019, 02:47:00~Jan 6, 2020, 02:47:00	Modify Delete

3. Then, you can:

- Search for alert contacts

Configure the corresponding product name, contact name, and phone number and then click **Search**. The alert contacts that meet the search conditions are displayed in the list.

- Add an alert contact

Click **Add**. On the displayed **Add Contact** page, complete the configurations and then click **OK**.

- Modify an alert contact

Find the alert contact to be modified and then click **Modify** in the **Actions** column. On the displayed **Modify Contact** page, modify the information and then click **OK**.

- Delete an alert contact

Find the alert contact to be deleted and then click **Delete** in the **Actions** column. Click **OK** in the displayed dialog box.

4.1.4.2 Alert contact groups

You can search for, add, modify, or delete an alert contact group based on business needs.

Procedure

1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **Alarm Monitoring** > **Alert Configuration**.
3. Click the **Contact Groups** tab.

Contacts						
Contact Groups		Static Parameter Settings				
Group Name		Search	Add	Delete All		
<input type="checkbox"/>	Group Name	Description	Phone Notifications	DingTalk Notifications	Email Notifications	Actions
<input type="checkbox"/>	> test	test	All Enabled	All Enabled	All Enabled	Modify Delete

4. Then, you can:

- Search for an alert contact group

Enter the group name in the search box and then click **Search**. The alert contact group that meets the search condition is displayed in the list.

- Add an alert contact group

Click **Add**. On the displayed **Add Contact Group** page, enter the group name and select the contacts to add to the contact group. Then, click **OK**.

- Modify an alert contact group

Find the alert contact group to be modified and then click **Modify** in the **Actions** column. On the displayed **Modify Contact Group** page, modify the group name, description, contacts, and notification method. Then, click **OK**.

- Delete one or more alert contact groups

Find the alert contact group to be deleted and then click **Delete** in the **Actions** column. In the displayed dialog box, click **OK**.

Select multiple alert contact groups to be deleted and then click **Delete All**. In the displayed dialog box, click **OK**.

4.1.4.3 Static parameter settings

You can configure the static parameters related to alerts based on business needs.

Currently, you can only configure the parameter related to timeout alerts.

Context

You cannot add new alert configurations in the current version. The system has a default parameter configuration for timeout alerts. You can modify the configuration as needed.

Procedure

1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **Alarm Monitoring > Alert Configuration**.
3. Click the **Static Parameter Settings** tab.
4. Optional: Enter the parameter name in the search box and then click **Search** to search for the static parameter configuration that meets the condition.
5. At the right of the static parameter to be modified, click **Modify** in the **Actions** column.

6. On the **Modify Static Parameter** page, modify the parameter name, parameter value, and description.

Configuration	Description
Parameter Name	Enter a parameter name related to the configuration.
Parameter Value	<p>The default value is 5, indicating 5 days.</p> <p>After completing the configuration, the system displays the alert events that meet the condition according to this parameter value on the Timeout Alert tab of Alarm Monitoring > Alert Events.</p> <p>For example, if the parameter value is 5, the system displays the alert events that exceed 5 days on the Timeout Alert tab of Alarm Monitoring > Alert Events.</p>

Configuration	Description
Description	Enter the description related to the configuration.

Modify Static Parameter

- Parameter Name: Alarm Time Out
- Parameter Code: ALARM_TIME_OUT
- Parameter Value: 5
- Description: Alarms that exceed a specified number of days are classified as overdue, Unit: day

OK Cancel

7. Then, click **OK**.

4.1.5 Alert overview

By viewing the alert overview, you can know the distribution of different levels of alerts for Apsara Stack products.

Procedure

1. [Log on to Apsara Stack Operations](#).

- In the left-side navigation pane, choose **Alarm Monitoring** > **Alert Overview**. The **Alert Overview** page appears.



- The column chart displays the number of unsolved alerts in the last seven days.
- The section at the bottom of the page displays the alert statistics in the current system by product.

4.1.6 Alert subscription and push

The alert subscription and push function allows you to configure the alert notification channel and then push the alert to operations engineers in certain ways.


Procedure

- Log on to [Apsara Stack Operations](#).
- In the left-side navigation pane, choose **Alarm Monitoring** > **Subscribe/Push**.

Subscribe Push															
Add Channel															
Channel Name	Subscribed Language	Subscription Region	Filter Condition	Protocol	Push Interface Address	Port Number	URI	HTTP Method	Push Cycle (Minutes)	Pushed Alerts	Push Mode	Push Template	Custom JSON Fields	Push Switch	Actions
test	zh-CN	cn-qd-hyq-d-01	Critical	http		8998	/test	POST	1	1	ALL	ANS		<input type="checkbox"/>	Modify Test Reset Delete
aso_test	zh-CN	cn-qd-hyq-d-01	base	http		80		POST	1	2	ALL	ASO		<input type="checkbox"/>	Modify Test Delete

- On the **Subscribe** tab, click **Add Channel**.
- On the **Add Subscription** page, complete the following configurations.

Configuration	Description
Channel Name	The name of the subscription channel.
Subscribed Language	Select Chinese or English.

Configuration	Description
Subscription Region	Select the region where the subscription is located.
Filter Condition	<p>Select a filter condition.</p> <ul style="list-style-type: none"> • Basic • Critical • Important • Minor • Custom filter
Protocol	Currently, only HTTP is supported.
Push Interface Address	The IP address of the push interface.
Port Number	The port number of the push interface.
URI	The URI of the push interface.
HTTP Method	Currently, only POST is supported.
Push Cycle (Minutes)	The push cycle, which is calculated by minute.
Pushed Alerts	The number of alerts pushed each time.
Push Mode	<p>Select one of the following methods:</p> <ul style="list-style-type: none"> • ALL: All of the alerts are pushed in each push cycle. • TOP: Only alerts with high priority are pushed in each push cycle.
Push Template	<p>Select one of the following templates:</p> <ul style="list-style-type: none"> • ASO: The default template. • ANS: Select this template to push alerts by DingTalk, SMS, or email. Currently, you can only configure one channel of this type. <div>  <p>Note: A preset ANS template exists if the system already connects with the ANS product. To restore the initial configurations of the template with one click, click Reset.</p> </div>
Custom JSON Fields	The person who receives the push can use this field to configure the identifier in a custom way. The format must be JSON.

Configuration	Description
Push Switch	Select whether to push the alerts. If the switch is not turned on here, you can enable the push feature in the Push Switch column after configuring the subscription channel.

- After completing the configurations, click **OK**.

To modify or delete a channel, click **Modify** or **Delete** in the **Actions** column.

- Optional: The newly added channel is displayed in the list. Click **Test** in the **Actions** column to test the connectivity of the push channel.



Note:

For the ANS push channel, you must enter the mobile phone number, email address, and/or DingTalk to which alerts are pushed after clicking **Test** in the Actions column.

- After configuring the push channel and turning on the push switch, you can click the **Push** tab to view the push records.

4.1.7 Alert masking

The Alert Masking module allows you to mask a type of alerts and remove the masking as needed.


4.1.7.1 Add a masking rule

By adding a masking rule, you can mask alerts that you are not required to pay attention to.


Procedure

- Log on to [Apsara Stack Operations](#).
- In the left-side navigation pane, choose **Alarm Monitoring** > **Alert Masking**.
- Click **Add** on the page.
- On the **Add** page, complete the configurations to mask a certain type of alerts.

Configuration	Description
Product	Optional. The product to which alerts to be masked belong.
Cluster	Optional. The cluster to which alerts to be masked belong.

Configuration	Description
Service	Optional. The name of the service to which alerts to be masked belong.
Alert Item	<p>Optional. The alert name to be masked.</p> <div> Note: If the number of alerts is large, you may have to wait for a few minutes when selecting an alert item.</div>
Monitoring Metric	Optional. The monitoring metric to which alerts to be masked belong.

Configuration	Description
Alert Plan	<p>Optional. The alert details of the alerts to be masked.</p> <p>Example:</p> <pre>{"serverrole":"ecs-yaochi.ServiceTest#","machine":"vm010012016074","level":"error"}</pre>
Severity	<p>Optional. Alerts are classified into the following levels:</p> <ul style="list-style-type: none"> • P0: indicates the cleared alerts, corresponding to alerts whose Alert Level is Restored in Monitoring > Alert History of Apsara Infrastructure Management Framework. • P1: indicates the critical alerts, corresponding to alerts whose Alert Level is P1 in Monitoring > Alert History of Apsara Infrastructure Management Framework. • P2: indicates the major alerts, corresponding to alerts whose Alert Level is P2 in Monitoring > Alert History of Apsara Infrastructure Management Framework. • P3: indicates the minor alerts, corresponding to alerts whose Alert Level is P3 in Monitoring > Alert History of Apsara Infrastructure Management Framework. • P4: indicates the remind alerts, corresponding to alerts whose Alert Level is P4 in Monitoring > Alert History of Apsara Infrastructure Management Framework. • P5: indicates the system alerts, corresponding to alerts whose Alert Level is P5 in Monitoring > Alert History of Apsara Infrastructure Management Framework.



Add [X]

Product
Select [v]

Cluster
Select [v]

Service
Select [v]

Alert Item
[]

Monitoring Metric
Select [v]

Alert Plan
Enter data in JSON format.

Severity
Select [v]

OK Cancel

**Note:**

If the number of alerts is large, you may have to wait for a few minutes when selecting an alert item.

5. Then, click **OK**.

Result

The added masking rule is displayed in the alert masking list.

In **Alarm Monitoring > Alert Events** and **Alarm Monitoring > Alert History**, you cannot view alerts that meet the conditions in the masking rule.

4.1.7.2 Remove the masking

You can remove the masking for masked alerts.

Procedure

1. Log on to Apsara Stack Operations.
2. In the left-side navigation pane, choose **Alarm Monitoring** > **Alert Masking**.
3. Optional: Select a product, service, or alert item, and then click **Search**.
4. Find the alert masking rule and then click **Delete** in the **Actions** column to remove the masking.

Product	Cluster	Service	Alert Item	Monitoring Metric	Alert Source	Severity	Actions
aso		aso-tools	tianji_ping_monitor_alarm			P0	Delete

5. In the displayed dialog box, click **OK**.

Result

After removing the masking, you can view alerts masked by the deleted masking rule in **Alarm Monitoring** > **Alert Events** and **Alarm Monitoring** > **Alert History**.

4.2 Physical servers

Operations personnel can monitor and view the physical servers where each product is located.

4.2.1 View the physical server information

You can view the physical server list and the details of physical servers in the system.

Product tab

1. In the left-side navigation pane of ASO, choose **Resource Management** > **Physical Servers**.

By default, the **Product** tab appears. In the upper-right corner, the number of current physical servers, the number of servers with alerts, and the number of alerts are displayed.

Product	Host Name	Cluster	Group	IP Address	Host Server	Alarms	Operation
nts	a58a0900		DbAnalyticdb			1	Details
nts	a58a0911c		DbAnalyticdb			1	Details





2. On this tab, view the physical server information.

- Expand the navigation tree on the left level by level to view the list of physical servers where a cluster of a product is located.
- Enter the product name, cluster name, group name, or hostname in the search box in the upper-left corner to quickly locate the corresponding node.
- In the search box on the right, search for physical servers by product, cluster, group, or hostname and view the details of a physical server.
- Click **Details** in the **Operation** column at the right of a product to go to the **Physical Server Details** page. Then, view the basic information, monitoring details, and alert information of the physical server to which the product belongs.

You can switch the tab to view the monitoring details and alert information.

The Monitoring Details tab displays the CPU usage, system load, disk usage, memory usage, network throughput, and disk I/O. When viewing the monitoring information, you can select the monitoring item in the upper-right corner of each monitoring graph and then select the time range to view the monitoring value in the specific time range.

In the upper-right corner of the CPU Usage, System Load, Disk Usage, Memory Usage, Network Throughput, and Disk IO sections, you can:

- Click the  icon to view the monitoring graph in full screen.
- Click the  icon to download the monitoring graph to your local computer.
- Click the  icon to manually refresh the monitoring data.
- Click the  icon and then the icon changes to green. The system automatically refreshes the monitoring data every 10 seconds. To disable the auto refresh function, click the icon again.

Server tab


1. In the left-side navigation pane of ASO, choose **Resource Management > Physical Servers**.

By default, the **Product** tab appears. In the upper-right corner, the number of current physical servers, the number of servers with alerts, and the number of alerts are displayed.

2. Click the **Server** tab.

3. On this tab, view the physical server list.

- Expand the navigation tree on the left by data center > rack to view the physical server list in a rack.
- Enter the rack name in the search box in the upper-left corner and then press Enter to search for and view the list of all the physical servers in the rack.



The screenshot shows the 'Server' tab interface. On the left, a navigation tree is expanded to 'A03' under 'amtest10'. The main area displays a table of physical servers. At the top right, status indicators show: 'The number of physical servers: 10', 'Number of servers with alerts: 10', and 'The number of alerts: 64'.

Host Name	Device Function	IP Address	SN	Alarms	Operation
a56a0900	Worker			1	Details Modify Delete
a56a0901	Worker			0	Details Modify Delete





4. To view the details of a physical server, enter the hostname, IP address, device function, or serial number (SN) in the search box on the right and then press Enter to search for the physical server whose details you are about to view.

5. Find the physical server whose details you are about to view and then click **Details** in the **Operation** column. On the **Physical Server Details** page, view the basic information, monitoring details, and alert information of the physical server.

You can switch the tab to view the monitoring details and alert information.

The Monitoring Details tab displays the CPU usage, system load, disk usage, memory usage, network throughput, and disk I/O. When viewing the monitoring information, you can select the monitoring item in the upper-right corner of each monitoring graph and then select the time range to view the monitoring value in the specific time range.

In the upper-right corner of the CPU Usage, System Load, Disk Usage, Memory Usage, Network Throughput, and Disk IO sections, you can:

- Click the  icon to view the monitoring graph in full screen.
- Click the  icon to download the monitoring graph to your local computer.
- Click the  icon to manually refresh the monitoring data.
- Click the  icon and then the icon changes to green. The system automatically refreshes the monitoring data every 10 seconds. To disable the auto refresh function, click the icon again.


4.2.2 Add a physical server

Operations personnel can add the information of existing physical servers in the environment to Apsara Stack Operations (ASO).

Procedure

1. In the left-side navigation pane of ASO, choose **Resource Management > Physical Servers**.

By default, the **Product** tab appears. In the upper-right corner, the number of current physical servers, the number of servers with alerts, and the number of alerts are displayed.

2. Click the **Server** tab.
3. Click the  icon in the upper-right corner of the **Server** tab.
4. On the displayed **Add Physical Server** page, configure the physical server information.

For more information about the configurations, see the following table.

Configuration	Description
Zone	The name of the zone where the physical server to be added is located.
Data Center	The name of the data center where the physical server to be added is located.
Rack	The rack where the physical server to be added is located.
Room	The room where the physical server to be added is located.
Physical Server Name	The name of the physical server to be added.
Memory	The memory of the physical server to be added.
Disk Size	The disk size of the physical server to be added.
CPU Cores	The CPU cores of the physical server to be added.
Rack Group	The rack group to which the physical server to be added belongs.
Server Type	The server type of the physical server to be added.
Server Role	The function or purpose of the physical server to be added.
Serial Number	The serial number (SN) of the physical server to be added.

Configuration	Description
Operating System Template	The template used by the operating system of the physical server to be added.
IP Address	The IP address of the physical server to be added.

5. Click **OK**.

4.2.3 Modify a physical server

You can modify the physical server information in the system when the information is changed in the Apsara Stack environment.


1. In the left-side navigation pane of ASO, choose **Resource Management > Physical Servers**.

By default, the **Product** tab appears. In the upper-right corner, the number of current physical servers, the number of servers with alerts, and the number of alerts are displayed.

2. Click the **Server** tab.

3. Optional: In the search box on the right, search for the physical server to be modified by hostname, IP address, device function, or serial number (SN).

4. Find the physical server to be modified and then click **Modify** in the **Operation** column.



The number of physical servers: 00 Number of servers with alerts: 10 The number of alerts: 04					
Host Name	Device Function	IP Address	SN	Alarms	Operation
a58a0900	Worker			1	Details Modify Delete
a58a0901	Worker			0	Details Modify Delete
a58a0902	Worker			0	Details Modify Delete

5. On the displayed **Modify Physical Server** page, modify the physical server information.

You can modify the following physical server information: zone, data center, rack, room, physical server name, memory, disk size, CPU cores, rack group, server type, server role, serial number, operating system template, and IP address.

6. Click **OK**.

4.2.4 Export the physical server information


You can export the information, including the zone, hostname, disk size, CPU cores, data center information (data center, rack, room, and rack group), server type, device function,

serial number (SN), operating system template, IP address, CPU architecture, and number of alerts, of all the physical servers in the system for offline review.

Product tab

1. In the left-side navigation pane of ASO, choose **Resource Management > Physical Servers**.


By default, the **Product** tab appears. In the upper-right corner, the number of current physical servers, the number of servers with alerts, and the number of alerts are displayed.

2. In the upper-right corner, click the  icon to export the information of all the physical servers from the dimension of products to your local computer.

Server tab

1. In the left-side navigation pane of ASO, choose **Resource Management > Physical Servers**.

By default, the **Product** tab appears. In the upper-right corner, the number of current physical servers, the number of servers with alerts, and the number of alerts are displayed.

2. Click the **Server** tab.
3. Click the  icon in the upper-right corner of the **Server** tab to export the information of all the physical servers from the dimension of servers to your local computer.

4.2.5 Delete a physical server

You can delete a physical server that does not require to be monitored based on business needs.

1. In the left-side navigation pane of ASO, choose **Resource Management > Physical Servers**.

By default, the **Product** tab appears. In the upper-right corner, the number of current physical servers, the number of servers with alerts, and the number of alerts are displayed.

2. Click the **Server** tab.
3. Optional: In the search box on the right, search for the physical server to be deleted by hostname, IP address, device function, or serial number (SN).

4. Find the physical server to be deleted and then click **Delete** in the **Operation** column.
5. In the displayed dialog box, click **OK**.

4.3 Inventory Management

The Inventory Management module allows you to view the current usage and inventory of various product resources, and manage resources in the system effectively.

4.3.1 View the RDS inventory


By viewing the RDS inventory, you can know the current usage and surplus of RDS product resources to perform Operations & Maintenance (O&M) operations according to actual requirements.

Procedure

1. In the left-side navigation pane of ASO, choose **Inventory Management > RDS Instances**.



Note:

You can click the  icon in the upper-right corner to configure the inventory thresholds of each engine.

2. View the RDS inventory.

Where,

- The **RDS Inventory** section displays the inventories of different types of RDS instances in the last five days. Different colors represent different types of RDS instances.
- The **RDS Inventory Details** section allows you to perform a paging query on the RDS inventory details by **Engine** and **Date**.

4.3.2 View the OSS inventory


By viewing the Object Storage Service (OSS) inventory, you can know the current usage and surplus of OSS product resources to perform Operations & Maintenance (O&M) operations according to actual requirements.

Procedure

1. In the left-side navigation pane of ASO, choose **Inventory Management > OSS Instances**.



Note:

You can click the  icon in the upper-right corner to configure the inventory thresholds.

2. View the OSS inventory.

Where,

- The **Inventory Availability History(G)** section displays the available OSS inventory in the last five days.
- The **Current Inventory Usage(G)** section displays the used OSS inventory and the corresponding percentage.
- The **OSS Bucket Inventory Details** section allows you to perform a paging query on the OSS inventory details by **Date**.

4.4 Storage Operation Center

The Storage Operation Center module contains the pangu section and miniOSS section.

4.4.1 Pangu

The Pangu section displays the pangu grail, cluster information, node information, and pangu cluster status.

4.4.1.1 Pangu grail

The Pangu Grail module allows you to view the overview, heatmap of health, and top 5 data of a product.

Procedure

1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **Storage Operation Center > Pangu > Pangu Grail**.
3. Select the product that you are about to view from the **Service** drop-down list.

Pangu Grail displays the data overview, heatmap of health, and top 5 data of each accessed cloud product as of the current date.

- **Overview**

Overview displays the storage space, server information, and health information of the selected product. Values of **Abnormal Disks**, **Abnormal Masters**, **Abnormal**

4.4.1.2 Cluster information

The Cluster Information module allows you to view the overview and run chart of a cluster.

Procedure

1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **Storage Operation Center > Pangu > Cluster Information**.

By default, data of the first cluster in the Cluster Name drop-down list is displayed.

3. Select the cluster that you are about to view from the **Cluster Name** drop-down list.

**Note:**

All the accessed clusters that are not in the closed status in the current environment are available for you to select from the **Cluster Name** drop-down list.

- **Overview**

Displays the storage space, server information, and health information of the selected cluster. Values of **Abnormal Water Levels**, **Abnormal Masters**, **Abnormal Chunk**

Servers, and **Abnormal Disks** in the **Health** section are displayed in red if they are larger than zero.

Overview

Storage		Server		Health			
Storage	866.38T	Servers	8	Abnormal Water Levels	0	Log Warning Num	0
Percentage	25.5400%	Abnormal Masters/Masters	0/3	Abnormal Masters	0	Log Error Num	0
Chunk Servers	8	Abnormal Chunk Servers/Chunk	0/8	Abnormal Chunk Servers	0	Log Fatal Num	0
Files	2,802,519	Abnormal Disks/Disks	0/120	Abnormal Disks	0	Replica Error Num	0


- **Alarm Monitor**

Displays the alert information of the selected cluster. You can perform a fuzzy search based on a keyword.

Alarm Monitor

Alarm Log

Warning:0 Error:0 Fatal:0

Fuzzy Search: 

Level	Desc
No data is available	

< Prev 1 Next >

- **Replica**

Displays the replica information of the selected cluster.

- **Run Chart of Clusters**

Displays the charts of historical water levels, predicted water levels, number of files, number of chunk servers, and number of disks for the selected cluster.

Predicted Water Levels predicts the run chart of the next seven days.



Note:

Predicted Water Levels has values only if Historical Water Levels has a certain amount of data. Therefore, some clusters may only have historical water levels, without predicted water levels.




- **Rack Information**

Consists of Servers in Rack and Storage.

- **Servers in Rack** displays the number of servers in each rack of the selected cluster.



- **Storage** displays the total storage and used storage in each rack of the selected cluster.



4.4.1.3 Node information

The Node Information module allows you to view the master information and chunk server information in a cluster.

Procedure

1. [Log on to Apsara Stack Operations.](#)

2. In the left-side navigation pane, choose **Storage Operation Center > Pangu > Node Information**.

By default, data, namely the master information and chunk server information, of the first cluster in the Cluster Name drop-down list is displayed.

3. Select the cluster that you are about to view from the **Cluster Name** drop-down list.



Note:

All the accessed clusters that are not in the closed status in the current environment are available for you to select from the **Cluster Name** drop-down list.

- **Master Info**

Displays the master information in the selected cluster. Partial refresh is supported. You can click **Refresh** to refresh the master information in the selected cluster.

Server	Role
[IP Address]	PRIMARY
[IP Address]	SECONDARY
[IP Address]	SECONDARY

- **Chunk Server Info**

Displays the chunk server information in the selected cluster. Partial refresh is supported. You can click **Refresh** to refresh the chunk server information in the selected cluster.

Click **+** to display the disk overview and SSDCache overview in the current chunk server. Fuzzy search is supported.

Server	IP	DiskBroken Disks/Chks	SSDCacheBroken Disks/Chks	Status	Backup	Storage (TB)	Usage(%)
+ a56b08006.cloud.b08.amtest27	[IP]	0/12	0/2	NORMAL	-	90.0742	26.8500%
+ a56b08001.cloud.b08.amtest27	[IP]	0/12	0/2	NORMAL	-	90.0742	26.8700%
+ a56b08009.cloud.b08.amtest27	[IP]	0/36	0/1	NORMAL	-	261.7032	22.5700%
+ a56b08003.cloud.b08.amtest27	[IP]	0/12	0/2	NORMAL	-	90.0742	26.5000%
+ a56b08007.cloud.b08.amtest27	[IP]	0/12	0/2	NORMAL	-	90.0742	26.5300%
+ a56b08009.cloud.b10.amtest27	[IP]	0/12	0/2	NORMAL	-	69.5000	24.5700%
+ a56b08004.cloud.b08.amtest27	[IP]	0/12	0/2	NORMAL	-	90.0742	26.5000%
+ a56b08005.cloud.b08.amtest27	[IP]	0/12	0/2	NORMAL	-	90.0742	26.8500%

4.4.1.4 Pangu operation


The **Pangu Operation** module allows you to view the pangu cluster status.

Procedure

1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **Storage Operation Center > Pangu > Pangu Operation**.
3. Select a product from the **Service** drop-down list to view the pangu cluster status of this product.

Clusters in different statuses are in different colors.

- Green indicates that the cluster works properly.
- Yellow indicates that the cluster has a warning.
- Red indicates that the cluster has an exception.
- Dark red indicates that the cluster has a fatal error.
- Grey indicates that the cluster is closed.



4. Move the pointer over a cluster name to view the service name, server name, and IP address to which the cluster belongs.

4.4.1.5 Product settings

By default, the system configures the alert threshold for each cluster. You can adjust the water level threshold, chunk server threshold, and disk threshold of each cluster based on business needs.

Procedure

1. Log on to Apsara Stack Operations.
2. In the left-side navigation pane, choose **Storage Operation Center > Pangu > Product Settings**.
3. Select the cluster you are about to configure from the **Cluster Name** drop-down list.

4. Click **Modify** at the bottom of the page to modify the threshold information of the cluster.

For more information about the threshold configurations, see the following table.

Configuration		Description
Cluster Water Level	Warn Threshold	<p>If the storage capacity utilization of the cluster is greater than or equal to this value, the alert at the warning level is triggered and the heatmap of health of this cluster is displayed in yellow. You can enter a value greater than zero and less than or equal to 100.</p> <p>If not configured, the alert at the warning level is triggered when the water level of the cluster is greater than or equal to 65% by default.</p>
	Error Threshold	<p>If the storage capacity utilization of the cluster is greater than or equal to this value, the alert at the error level is triggered and the heatmap of health of this cluster is displayed in red. You can enter a value greater than zero and less than or equal to 100.</p> <p>If not configured, the alert at the error level is triggered when the water level of the cluster is greater than or equal to 85% by default.</p>
	Fatal Error Threshold	<p>If the storage capacity utilization of the cluster is greater than or equal to this value, the alert at the fatal error level is triggered and the heatmap of health of this cluster is displayed in dark red. You can enter a value greater than zero and less than or equal to 100.</p> <p>If not configured, the alert at the fatal error level is triggered when the water level of the cluster is greater than or equal to 92% by default.</p>

Configuration		Description
Chunk Server	Warn Threshold (Abnormal Chunk Server Quantity)	<p>If the number of abnormal chunk servers is greater than or equal to this value, the alert at the warning level is triggered and the heatmap of health of this cluster is displayed in yellow.</p> <p>If not configured, the alert at the warning level is triggered when the number of abnormal chunk servers is greater than or equal to 1 by default.</p>
	Error Threshold (Abnormal Chunk Server Ratio)	<p>If the ratio of abnormal chunk servers to all the chunk servers is greater than this value, the alert at the error level is triggered and the heatmap of health of this cluster is displayed in red.</p> <p>If not configured, the alert at the error level is triggered when the ratio of abnormal chunk servers to all the chunk servers is greater than or equal to 10% by default.</p>
Disk	Warn Threshold (Abnormal Disk Quantity)	<p>If the number of abnormal disks is greater than or equal to this value, the alert at the warning level is triggered and the heatmap of health of this cluster is displayed in yellow.</p> <p>If not configured, the alert at the warning level is triggered when the number of abnormal disks is greater than or equal to 1 by default.</p>

Configuration		Description
	Error Threshold (Abnormal Disk Ratio)	<p>If the ratio of abnormal disks to all the disks is greater than this value, the alert at the error level is triggered and the heatmap of health of this cluster is displayed in red.</p> <p>If not configured, the alert at the error level is triggered when the ratio of abnormal disks to all the disks is greater than or equal to 10% by default.</p>

**Note:**

To reset the configurations during the modification, click **Cancel** to cancel the current configurations.

5. Then, click **Save**.

4.4.2 miniOSS

The miniOSS module provides you with the following functions: monitoring dashboard, user management, permission/quota management, array monitoring, and system management.

4.4.2.1 Monitoring dashboard

The Monitoring Dashboard module allows you to view the overview, bucket watermark heatmap, user quota watermark heatmap, watermark trend, and network traffic trend of miniOSS in the system, and download logs to your local computer.

Procedure

1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **Storage Operation Center > miniOSS > Monitoring Dashboard**.

3. On this page, you can view the following information:

- **Overview**

Displays the bucket information, user information, and health information of miniOSS.

Values of **Abnormal Bucket Watermarks** and **Abnormal User Quota Watermarks** in the **Health** section are displayed in red if they are larger than zero.

Overview					
Bucket Information		User Information		Health	
Buckets	182	Users	74	Abnormal Bucket Watermarks	0
Total Size	744942GB	Bucket Size Allocated to User	744941GB	Abnormal User Quota Watermarks	0
Percentage	0.49%	Used Bucket Size (%)	0.00%		


- **Bucket Watermark Heatmap**

Displays the bucket capacity usage.

The number of sections in **Bucket Watermark Heatmap** is the same as the value of Buckets in **Overview**. Buckets in different colors represent different statuses. Where,

- Green indicates the normal status.
- Yellow indicates a warning.
- Red indicates the abnormal status.
- Dark red indicates a fatal error.
- Grey indicates the closed status.

Move the pointer over a bucket section to view the percentage of capacity used by the bucket.



- **User Quota Watermark Heatmap**

Displays the user quota watermark information.

User quota watermark = used capacity of all buckets of the user/total capacity of all buckets of the user. Different watermark values are displayed in different colors.

Where,

- Green indicates the normal status.
- Yellow indicates a warning.
- Red indicates the abnormal status.
- Dark red indicates a fatal error.
- Grey indicates the closed status.

Move the pointer over a section to view the percentage of capacity used by all buckets of a user.

- **Watermark Trend**

Displays the historical water levels and predicted water levels of a user or bucket.

Watermark represents the disk utilization, and watermark of a user indicates the disk utilization of a user's buckets.

Data in the watermark trend comes from scheduled tasks in the system. The system stores or updates data every 30 minutes.


Select a bucket or user from the drop-down list to view the corresponding watermark trend.



Note:

You can enter a keyword of a **Bucket Name** or **Username** to perform a fuzzy search.

The top 10 data in terms of the bucket watermarks are displayed on the right. Click a bucket name in the top 10 data to view the watermark trend of the bucket on the left.




• Network Traffic Trend


Displays the daily network traffic data, namely the normal network traffic, abnormal network traffic, average weekly network traffic, and average monthly network traffic, of miniOSS in the last month.

In the network traffic trend:

- Green indicates the network traffic is normal.
- Yellow indicates the network traffic is abnormal.
- Orange indicates the average weekly network traffic.
- Blue indicates the average monthly network traffic.



- Optional: You can click **Download Log Package** in the **Download Log** section and then use the download URL to download logs to your local computer for subsequent review and analysis.



4.4.2.2 User management

The User Management module consists of User List, Bucket List of User, and Network Traffic Control. You can use this module to view the user information, bucket list of a user, and network traffic bandwidth.

Procedure

1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **Storage Operation Center > miniOSS > User Management**.
3. On this page, you can:

- View the user information

All of the users, including the administrator and common users, are displayed in the list by default.


Click **View All** in the **Actions** column at the right of a user and view the SecretKey of the user in the displayed dialog box.

In the **User List** section, enter a keyword with three characters of the username, such as def, and press Enter or click the search icon. Then, you can view the information, namely the username, user role, AccessKey, and network traffic bandwidth, of the user that meets the search condition.



Note:

After the search, to view all of the users in the list, click **Refresh**.



Username	User Role	AccessKey	Network Traffic Control	Actions
MiniosUser1	Administrator	[REDACTED]	0MB	View All
MiniosUser2	Common User	[REDACTED]	10MB	View All
MiniosUser3	Common User	[REDACTED]	0MB	View All
adb01	Common User	[REDACTED]	0MB	View All
ascuser-ascm-dw-1583944061985	Common User	[REDACTED]	1MB	View All

- View the bucket information of a user


Click a username in the **User List** section. Then, view the bucket information, namely the bucket name, bucket ACL, user ACL, quota, and bucket creation time, of the user in the **Bucket List of User** section.

In the **Bucket List of User** section, enter a keyword with five characters of the bucket name, such as atest, and press Enter or click the search icon. Then, you can view the information of the bucket that meets the search condition.



Note:

After the search, to view the information of all buckets, click **Refresh**.



Bucket Name	Bucket ACL	User ACL	Quota	Created At
adb-test01	Private Write	Private Write	0GB	2019-09-03 11:14:16

- Add a bucket for a common user



Notice:


You can only add a bucket for a common user, instead of for an administrator.

Find the common user for whom you are about to add a bucket in the **User List** section and then click the username. In the **Bucket List of User** section, click **Add**. In the displayed dialog box, select the bucket and user ACL, enter the quota, and then click **OK**.



Note:

Enter an integer from 0 to 4094 as the quota.




The 'Allocate Bucket' dialog box has a dark blue background. It contains three fields: 'Bucket:' with a dropdown menu showing 'adb-test01', 'User ACL:' with a dropdown menu showing 'Private Write', and 'Quota:' with a text input field and a 'GB' label to its right. At the bottom right, there are two buttons: 'Cancel' and 'OK'.

- View the network traffic bandwidth of a user

Find the user whose network traffic bandwidth you are about to view in the **User List** section and then click the username. View the network traffic bandwidth of the user in the **Network Traffic Control** section.

- Modify the network traffic bandwidth of a user

Find the user whose network traffic bandwidth you are about to modify in the **User List** section and then click the username. In the **Network Traffic Control** section, click **Modify** to modify the network traffic bandwidth of the user and then click **Save**. The value of network traffic bandwidth must be 0 or a positive integer.



The 'Network Traffic Control' section shows a table with two rows. The first row has 'Username' and 'MiniossUser2'. The second row has 'Network Traffic Bandwidth' and '10MB'. A blue 'Modify' button is located at the bottom right of the section.

4.4.2.3 Permission and quota management

The Permission/Quota Management module allows you to view the bucket list and user list of bucket, and add, modify, and delete a bucket.

Procedure

1. [Log on to Apsara Stack Operations.](#)
2. In the left-side navigation pane, choose **Storage Operation Center > miniOSS > Permission/Quota Management**.

3. On this page, you can:

- View the bucket information

All of the buckets are displayed in the bucket list by default. In the **Bucket List** section, you can view the basic information, namely bucket name, bucket ACL, quota, and network traffic bandwidth, of all the buckets.

Enter a keyword of the bucket name in the search box in the upper-left corner and press Enter or click the search icon. Then, you can view the information of the bucket that meets the search condition.

**Note:**

After the search, to view all the buckets in the list, click **Refresh**.

- Add a bucket

In the **Bucket List** section, click **Add**. In the displayed dialog box, enter the bucket name and then click **OK**. The bucket name must be 3 to 63 characters in length, can only contain lowercase letters, digits, hyphens (-), and cannot start or end with a hyphen (-).

- Modify a bucket

In the **Bucket List** section, click **Modify** in the **Actions** column at the right of the bucket to be modified. In the displayed dialog box, modify the bucket ACL, quota, and network traffic bandwidth, and then click **OK**.

- Delete a bucket

In the **Bucket List** section, click **Delete** in the **Actions** column at the right of the bucket to be deleted. Click **OK** in the displayed dialog box.

- View the information of the user that a bucket belongs

In the **Bucket List** section, click a bucket name to view the user information related to the bucket in the **User List of Bucket** section.

Enter a keyword of the username in the search box and press Enter or click the search icon. Then, you can view the information of the user that meets the search condition.

**Note:**

After the search, to view the information of all the users, click **Refresh**.

4.4.2.4 Array monitoring

The Array Monitoring module allows you to know the running status of each device.

Procedure

1. [Log on to Apsara Stack Operations.](#)
2. In the left-side navigation pane, choose **Storage Operation Center > miniOSS > Array Monitoring.**
3. View the running status of each device.

By default, you can view the status information of all devices.

The device types are as follows: rack, controller, hard drive, rack battery, Power Supply Unit (PSU), fan, FC port, iSCSI port, SAS port, USB port, cluster node, cluster system, block storage, volume information, storage pool information, server, NFS service, CIFS service, FTP service, and file system.

Array Monitoring (Click to go to the array GUI)

Type	ID	Status	Type	ID	Status
Rack	1	Online	SAS Port	9	Offline
Type	ID	Status		0	Offline
Controller	1	Online		1	Online
	2	Online		2	Online
Type	ID	Status		8	Offline
Hard Drive	0	Online		10	Online
	3	Online	Type	ID	Status
	11	Online	USB Port	0	Normal
	1	Online		8	Normal
	8	Online		9	Normal
	6	Online		1	Normal

Values in different colors represent different statuses.

- Green indicates the online or normal status.
- Yellow indicates the offline status.
- Red indicates the abnormal status.

On top of the page, click **Click** to go to the array GUI.

4.4.2.5 System management

The System Management module allows you to modify the bucket watermark threshold and user watermark threshold.

Procedure

1. [Log on to Apsara Stack Operations.](#)

2. In the left-side navigation pane, choose **Storage Operation Center > miniOSS > System Management**.

3. On this page, you can:

- Modify the bucket watermark threshold
 - a. In the **Bucket Watermark Threshold** section, click **Modify**.
 - b. Enter a positive number equal to or less than 100 as the warning value, error value , and fatal error value. Make sure that the warning value is less than the error value and the error value is less than the fatal error value.
 - c. Then, click **Save**.
- Modify the user watermark threshold
 - a. In the **User Watermark Threshold** section, click **Modify**.
 - b. Enter a positive number equal to or less than 100 as the warning value, error value , and fatal error value. Make sure that the warning value is less than the error value and the error value is less than the fatal error value.
 - c. Then, click **Save**.

5 Operations tools

5.1 NOC

Network Operation Center (NOC) is an all-round operations tool platform that covers the whole network (virtual network and physical network).

5.1.1 Network topology

The Network Topology tab allows you to view the physical network topology.

Procedure

1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **NOC > Dashboard**.
3. On the **Network Topology** tab, view the physical network topology of a physical data center.

You can select **Standard Topology** or **Dynamic Topology** as the **Topology Type**.




Note:

The colors of the connections between network devices represent the connectivity between the network devices.

- Green: The link works properly.
- Red: The link has an error.

- Grey: The link is inactive.

If the **Topology Type** is **Standard Topology**, the **Refresh Alert** switch is turned on by default. You can turn off the **Refresh Alert** switch, and then devices or link statuses in the topology are not updated after new alerts are triggered.



4. In the topology, double-click a connection between two devices to view the links and alerts between the two devices.
5. In the topology, double-click a physical network device to view the basic information and node alerts of the device on the right.

5.1.2 Resource management

The Resource Management module is used to manage network-related resources, including the information of physical network element devices, virtual network products, and IP addresses.

5.1.2.1 Device management


The **Device Management** page displays the basic information, running status, traffic monitoring, and logs of physical network element devices, and allows you to configure the collection settings of network devices.

5.1.2.1.1 View the network monitoring information

The **Network Monitoring** tab allows you to view the basic information, running status, and traffic monitoring of Apsara Stack physical network devices, and know the health status of devices in the whole network in time.

Procedure

1. Log on to Apsara Stack Operations.
2. In the left-side navigation pane, choose **NOC > Resource Management > Network Elements**.
3. Click the **Network Monitoring** tab under **Device Management**.



Device Name	IP Address	SN	Manufacturer	Model	Role	Online Duration	Ping Status	SNMP Status	Last Updated Time	Details
ASW-A5-8-C01-AMTEST43			H3C	S6800-54QF	ASW	324 Days	Accessible	Accessible	Nov 30, 2019, 22:02:04	View
ISW-VM-G1-1-AMTEST37			H3C	S6800-54QF	ISW	401 Days	Accessible	Accessible	Nov 30, 2019, 22:02:04	View

4. Then, you can:
 - View the basic information, ping status, and SNMP status of Apsara Stack physical network devices.

**Note:**

You can also click **Export to CSV** to export the network device information to your local computer as required.

If a problem exists in the business connectivity or gateway connectivity, the value in the Ping Status column or SNMP Status column changes from green to red. Then, the operations personnel are required to troubleshoot the problem.

- In the search box in the upper-right corner, enter the device name or IP address to search for the monitoring information of a specific device.
- View the port information and alert information of a device.
 - a. Click a device name, or click **View** in the **Details** column at the right of a device.
 - b. Under **Port**, view the port list, port working status, and other link information of the device.
 - c. Under **Alert Info**, view the alert information of the device.

During the daily operations, you must pay close attention to the alert information list of the device. Normally, no data exists under **Alert Info**, indicating that the device works properly.

If alert events occur, unrecovered alert events are displayed in the list. You must handle these exception events in time. After you handle exceptions, the alert events are automatically cleared from the list.

- View the traffic information of a device for a specific port and time range.
 - a. Click a device name, or click **View** in the **Details** column at the right of a device.
 - b. Search for the port that you are about to view by using the search box in the upper-right corner of the **Port** section. Click **View** in the **Details** column at the right of the port.

Port		Alert Info		Port Name <input type="text"/>					
Port Name	Port Speed	Port Alias	Admin Status	Operation Status	End Device	End Port	End Port Alias	Last Updated Time	Details
Ten-GigabitEthernet1/0/1	10000	Link_SERVER-1	Up	Up	a56a09001.cloud.a09.amtest43	eth1	—	Oct 23, 2019, 19:22:38	View
Ten-GigabitEthernet1/0/10	10000	Link_SERVER-10	Up	Up	a56a09010.cloud.a09.amtest43	eth4	—	Nov 10, 2019, 23:38:15	View
Ten-GigabitEthernet1/0/11	10000	Link_SERVER-11	Up	Up	a56a09011.cloud.a09.amtest43	eth2	—	Oct 24, 2019, 13:59:41	View

- c. Select a time range on the right and then click **Search** to view the traffic in the selected time range.

You can select 5MIN, 30MIN, 1H, or 6H in the **Quick Query** section to view the traffic within 5 minutes, 30 minutes, 1 hour, or 6 hours.

5.1.2.1.2 View logs

The **Syslogs** tab allows you to view logs of physical network element devices, providing necessary data for fault location and diagnosis information collection if a fault occurs.


Context

During the daily inspection, you can search for logs generated by a specific network device during a specific time range on the **Syslogs** tab.

Procedure

1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **NOC > Resource Management > Network Elements**.
3. Click the **Syslogs** tab under **Device Management**.
4. In the upper-right corner, select the name of the device that you are about to view from the drop-down list, and then select a time range. Click **Search** to view if the device generates system logs during the selected time range.

No search results exist if the device has a configuration exception or does not generate any logs during the selected time range.



5. Optional: You can filter the search results based on the log keyword.
6. Optional: Click **Export to CSV** in the upper-right corner to export the search results to your local computer.

5.1.2.1.3 Collection settings

The Collection Settings tab allows you to configure the collection interval of physical network element devices and manage OOB network segments.

5.1.2.1.3.1 Modify the collection interval

You can modify the collection interval to adjust the time interval of collection.

Procedure

1. [Log on to Apsara Stack Operations.](#)
2. In the left-side navigation pane, choose **NOC > Resource Management > Network Elements**.
3. Click the **Collection Settings** tab under **Device Management**.
4. In the **Collection Interval Settings** section, modify the auto scan interval, device scan interval, port scan interval, and link scan interval.

**Note:**

To not save your modification before the submittal, click **Reset** in the upper-right corner to reset the collection interval to the former version.

5. Click **Submit**.

One minute later, the modified collection interval of network device information is synchronized to the system.

5.1.2.1.3.2 Add an OOB network segment

If this is the first time to use the Network Elements function of Network Operation Center (NOC), you must add the device loopback IP address range planned by the current Apsara Stack network device, which is generally the IP address range of the netdev.loopback field in the IP address planning list.

Context

The OOB Network Segments section is used to configure the management scope of a physical network element device. Generally, operations engineers are required to add the loopback IP address range where the network device to be managed resides.

In the Apsara Stack scenario, use the loopback IP address range to configure the management scope of a physical network element device. To expand the network and the loopback IP address range, you must add the IP address range involved in the expansion to the management scope. The way to add an expansion IP address range is the same as that to add the loopback IP address range for the first time. Then, you can search for the IP address range of the managed device on this page.

Procedure

1. [Log on to Apsara Stack Operations.](#)
2. In the left-side navigation pane, choose **NOC > Resource Management > Network Elements**.

3. Click the **Collection Settings** tab under **Device Management**.
4. In the **OOB Network Segments** section, click **Add Network Segment**.
5. In the displayed dialog box, enter the IP address range containing the mask information, subnet mask, and select a data center.

6. Click **Submit**.

The initial data is synchronized to the system after the submittal.

5.1.2.1.3.3 Modify the OOB network segment information

You can modify the network segment information of your managed device.

Procedure

1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **NOC > Resource Management > Network Elements**.
3. Click the **Collection Settings** tab under **Device Management**.
4. In the **OOB Network Segments** section, click **Refresh** in the upper-right corner to obtain the latest OOB network segment information.

ID	Management Network Segment	Subnet Mask	IDC	Created At	Modified At	Actions
16		255.255.255.0	amtest27	Nov 30, 2016, 23:33:27	Nov 30, 2016, 23:33:27	Edit Delete

5. Optional: Enter the network segment information in the search box and then press Enter or click the search icon.
6. Find the OOB network segment to be modified and then click **Edit** in the **Actions** column.

7. In the displayed dialog box, modify the Management Network Segment, Subnet Mask, or IDC, and then click **Submit Change**.

5.1.2.1.3.4 Delete an OOB network segment

You can delete an OOB network segment that you are not required to manage based on business needs.

Procedure

1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **NOC > Resource Management > Network Elements**.
3. Click the **Collection Settings** tab under **Device Management**.
4. Find the OOB network segment to be deleted and then click **Delete** in the **Actions** column.
5. Click **OK** in the displayed dialog box.

5.1.2.2 View the instance monitoring information

The **Instance Monitoring** tab allows you to view the basic information and water level of an instance, including the bps and pps.

Procedure

1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **NOC > Resource Management > Server Load Balancers**.
3. Click the **Instance Monitoring** tab.
4. Select the cluster where the instance that you are about to view is located from the Cluster drop-down list. Enter the VIP address that you are about to search for in the field and then click **Search**.
5. View the water level data of this VIP address.

Select a time range and then click **Search** or select 5MIN, 30MIN, 1H, or 6H in the Quick Query section to view the operating water level graph of the VIP address in a specific time range.

5.1.3 Alert management


The Alert Management module provides you with the real-time alert dashboard, history alert dashboard, and the alert settings function.

5.1.3.1 View and process current alerts

You can view and process current alerts on the **Current Alerts** tab.

Procedure

1. [Log on to Apsara Stack Operations.](#)
2. In the left-side navigation pane, choose **NOC > Alert Management > Alert Dashboard**.
3. Click the **Current Alerts** tab.



4. Enter a keyword in the search box in the upper-right corner and then click **Search**.
Alerts that meet the search condition are displayed.
5. Optional: You can filter the search results by device name, device IP address, or alert name.
6. Click **Details** in the **Details** column at the right of an alert to view the detailed alert information.
7. Find the reason why the alert is triggered and then process the alert.
 - If the alert does not affect the system normal operation, you can click **Ignore** in the **Actions** column to ignore the alert.
 - If the alert is meaningless, you can click **Delete** in the **Actions** column to delete the alert.

After processing an alert, you can search for it on the **History Alerts** tab.


8. Optional: Click **Export to CSV** to export the alert information to your local computer.

5.1.3.2 View history alerts

You can view history alerts on the **History Alerts** tab.

Procedure

1. [Log on to Apsara Stack Operations.](#)
2. In the left-side navigation pane, choose **NOC > Alert Management > Alert Dashboard.**
3. Click the **History Alerts** tab.



4. Select Alert Source, Alerting IP Address, Alerting Device, Alert Name, Alert Item, or Alerting Instance from the drop-down list and then enter a keyword in the field. Select a time range and then click **Search**.

Alerts that meet the search conditions are displayed.

5. Click **Details** in the **Details** column at the right of an alert to view the detailed alert information.
6. Optional: Click **Export to CSV** to export the alert information to your local computer.

5.1.3.3 Add a trap

If the initially configured trap subscription cannot meet the monitoring requirement, you can add a trap as required for monitoring match.

Context

The trap in this topic is the Simple Network Management Protocol (SNMP) trap. SNMP trap is a part of SNMP and a mechanism that devices being managed (here refers to network devices such as switches and routers) send SNMP messages to the Network Operation Center (NOC) monitoring server. If an exception exists on the side being monitored, namely the switch monitoring metrics have an exception, the SNMP agent running in a switch sends an alert event to the NOC monitoring server.

Procedure

1. [Log on to Apsara Stack Operations.](#)
2. In the left-side navigation pane, choose **NOC > Alert Management > Alert Settings.**
3. On the **Alert Settings** page, click **Configure Trap**.

4. In the displayed **Configure Trap** dialog box, complete the configurations.

For more information about the configurations, see the following table.

Configuration	Description	Example
Trap Name	The name of the alert event.	linkdown or BGPneighbor down. You can customize this value.
Trap OID	The OID of the alert event.	.1.3.6.1.4.1.25506.8.35.12.1.12 Configure the value strictly according to the device document. You cannot customize this value.
Trap Type	The type of the alert event. Select a value from the drop-down list.	-
Trap Index	The index ID of the alert item.	This value is the KV information in the trap message, which is used to identify the alert object. Generally, this value can be an API name, protocol ID, or index ID. Configure the value strictly according to the device document. You cannot customize this value.

Configuration	Description	Example
Trap Msg	The message of the alert item .	<p>This value is the KV information in the trap message, which is used to identify the alert data. Generally, this value can be the additional information of the alert item, such as a system message or a message indicating the location of the state machine or the current status.</p> <p>Configure the value strictly according to the device document. You cannot customize this value.</p>
Alert Type	Indicates whether this alert is of the fault type or the event type.	-

Configuration	Description	Example
Association	<p>Indicates whether this alert has an event alert.</p> <p>If Fault is selected as the Alert Type and this alert has an association alert, select Event Alert as Association and then add the trap of the association alert.</p>	-

5. Then, click **Submit**.

After the submittal, the system checks if the trap OID and trap name are the same as the existing ones. If not, the alert settings of the added trap are finished.

The system pays attention to the alert events of the configured trap OID and such alert events are displayed on the **Current Alerts** and **History Alerts** tabs of **Alert Management > Alert Dashboard**.

5.1.3.4 View a trap

You can view a trap configured in the current system.

Procedure

1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **NOC > Alert Management > Alert Settings**.

3. Enter a keyword in the search box in the upper-right corner and then click **Search**.

**Note:**

After the search results are displayed, you can click **Export to CSV** in the upper-right corner to export the trap information to your local computer.

4. Optional: You can filter the search results by trap name, trap type, or OID.
5. Find a trap and then move the pointer over **Details** in the **Actions** column to view the detailed trap information.

**Note:**

If a trap is no longer in use, you can click **Delete** in the **Actions** column at the right of the trap.

5.2 Task Management

The system allows you to run operations scripts on the cloud platform, which reduces your actions by using command lines, lowers misoperations, and improves the security and stability of the cloud platform.

5.2.1 Overview

The Task Management module has the following functions:

- Supports viewing task overview and creating tasks quickly.
- Supports the following four methods to run tasks: manual execution, scheduled execution, regular execution, and advanced mode.
- Supports the breakpoint function, which allows a task to stop between its two scripts and wait for manual intervention.
- Supports searching for tasks by name, status, and created time.
- Supports uploading the .tar package as the script.


5.2.2 View the task overview

The **Task Overview** page displays the overall running conditions of tasks in the system. You can also create a task on this page.

Procedure

1. [Log on to Apsara Stack Operations](#).

2. In the left-side navigation pane, choose **Task Management > Task Overview**.



3. On the Task Overview page, you can:

- In the **Dashboard** section, view the number of tasks in the **Pending for Intervention**, **Running**, **Failed**, or **Completed** status in the system.
Click the status or number to view the task list of the corresponding status.
- In the **Create Task** section, click **Create Task** to create an operations task.
For more information about how to create a task, see [Create a task](#).
- If a task has a breakpoint and runs to the breakpoint, the task stops and waits for manual confirmation. You can view and process tasks to be intervened in the **Tasks To Be Intervened** section.
- In the **Running Status in Last 7 Days** section, view the running trend of tasks and whether tasks are successful in the last seven days.
- In the **Running Tasks** section, view tasks running in the last 24 hours.


5.2.3 Create a task

You can create daily changes as tasks to run on the cloud platform.

Procedure

- [Log on to Apsara Stack Operations](#).
- In the left-side navigation pane, choose **Task Management > Task Management**.
- Click **Create**.

4. In the displayed dialog box, configure the task information.

Configuration	Description
Task Name	The name of the operations task.
Task Description	The description of the operations task.
Target Group	<p>The task target. You can configure the target group in the following ways:</p> <ul style="list-style-type: none">• Select from the drop-down list by product > cluster > service > server role > virtual machine (VM) or physical machine.• Select a product. Enter the VM or physical machine in the field and then press Enter. You can enter multiple VMs or physical machines in sequence.• Click the  icon next to Target Group. In the displayed dialog box, enter the target group, with one VM or physical machine in one line, and then click OK.

Configuration	Description
Execution Batch	<p>Optional. This option appears after you enter the target group.</p> <p>You can select the following options as the Execution Batch.</p> <ul style="list-style-type: none"> Default Order <p>If the number of machines is equal to or less than 10 , the machines are allocated to different batches by default, with one machine in batch 1, one machine in batch 2, two machines in batch 3, three machines in batch 4, and the other machines in batch 5. You can adjust the batch for machines as needed.</p> <p>If the number of machines is more than 10, the machines are allocated to different batches by default , with one machine in batch 1, three machines in batch 2, five machines in batch 3, $N/3-1$ (an integer) machines in batch 4, $N/3-1$ (an integer) machines in batch 5, until all of the machines are allocated. Where , N is the total number of servers in the cluster. You can adjust the batch for machines as needed.</p> Single-Machine Order: By default, each batch has one machine. You can adjust the batch for machines as needed. <p>If the execution batch is not selected, the Execution Batch switch is turned off by default, and Target Group is displayed in the Target Group column in the task list of the Task Management > Task Management page. If you select and save the execution batch, the Execution Batch switch is turned on automatically, and Batch Execution Policy is displayed in the Target Group column.</p>

Configuration	Description
Execution Method	<p>If you turn on the Execution Batch switch, the Execution Method can only be Manual Execution and cannot be selected.</p> <p>If the Execution Batch switch is not turned on, you can select one of the following execution methods:</p> <ul style="list-style-type: none">• Manual Execution: You must manually start the task. With this option selected, you must click Start in the Actions column to run the task after the task is created.• Scheduled Execution: Select the execution time. The task automatically runs when the time is reached.• Regular Execution: Select the interval and execution times to run the task. The task runs again if the execution condition is met.• Advanced: Enter the crontab expression to configure the command to run the task periodically. <p>For example, <code>0 20 20 * * ?</code> indicates that the task runs at 20:20 every day.</p>

Configuration	Description
Add Script	<p>Click Add Script. Select one or more .tar packages to upload the script file. After the upload, you can delete and reupload the script.</p> <p>After uploading the script, if Manual Execution is selected as the Execution Method, you must select whether to turn on the Intervention Required switch. If the switch is turned on, the task stops and waits for manual intervention after the script runs.</p>

Create Task

Task Name

test

Task Description

test

Target Group

aso

vm010004024198 x

vm010004028255 x

vm010004021104 x

vm010004028003 x

vm010004020034 x

vm010004029054 x

vm010004021098 x

vm010004024238 x

Execution Batch

☐ Default Order
☐ Single-Machine Order

Execution Method

Manual Execution

+ Add Script

Supported Extension: .tar

Create

5. Then, click **Create**.

Result

The created task is displayed in the task list.

5.2.4 View the execution status of a task

After a task runs, you can view the execution status of the task.

Procedure

1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **Task Management** > **Task Management**.
3. Optional: Enter the task name, select the task status, and configure the start time and end time of the task. Then, click **Query** to search for the task.
4. Find the task that you are about to view and then click **Target Group** or **Batch Execution Policy** in the **Target Group** column.




Note:

If the **Execution Batch** is not selected when you create a task, **Target Group** is displayed in the **Target Group** column. If you select the **Execution Batch** when creating a task, **Batch Execution Policy** is displayed in the **Target Group** column.

Tasks					
Task Name	Task Status	Start Date	End Date	Query	Create
Task Name	Task Description	Time	Task Status	Target Group	Actions
End Time :Nov 22, 2019, 14:09:49					
baoxun22	dds	Created At :Nov 15, 2019, 11:23:17 Start Time :Nov 22, 2019, 11:39:59 End Time :Nov 22, 2019, 11:40:37	Completed	Target Group	Modify Start Delete
44		Created At :Nov 15, 2019, 10:51:16 Start Time :Nov 15, 2019, 10:51:22 End Time :Nov 15, 2019, 10:52:10	Completed	Batch Execution Policy	Modify Start Delete
test1		Created At :Nov 11, 2019, 14:43:49 Start Time :Nov 11, 2019, 14:43:52 End Time :Nov 11, 2019, 14:44:04	Completed	Batch Execution Policy	Modify Start Delete

5. In the displayed dialog box, view the task execution status based on the machine color. Click a machine to view the execution result of the task.



5.2.5 Start a task

If you select **Manual Execution** when creating a task, you must manually start the task after the task is created.

Procedure

1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **Task Management > Task Management**.
3. Optional: Enter the task name, select the task status, and configure the start time and end time of the task. Then, click **Query** to search for the task.
4. Find the task that you are about to start and then click **Start** in the **Actions** column.
5. In the displayed dialog box, select the batches to start and then click **Start**.

For a new task, the system indicates that the task is started after you click **Start** for the first time. The virtual machines (VMs) or physical machines in batch 1 start to run the

task. Click **Start** again and you can select VMs or physical machines in one or more batches to run the task.

If the task has the Intervention Required switch turned on, you must intervene the task after clicking **Start**. The **Task Status** changes to **Pending for Intervention** and you can only continue to run the task by clicking **Continue** in the **Actions** column.

Tasks					
Task Name	Task Status	Start Date	End Date	Query	Create
Task Name	Task Description	Time	Task Status	Target Group	Actions
test03		Created At :Dec 30, 2019, 14:34:17 Start Time :Dec 30, 2019, 14:39:47 End Time :Dec 30, 2019, 14:40:06	Failed	Target Group	Modify Start Delete
test02		Created At :Dec 30, 2019, 11:03:32 Start Time :Dec 30, 2019, 14:43:14 End Time :Dec 30, 2019, 14:43:40	Completed	Batch Execution Policy	Modify Start Delete
test01	test	Created At :Dec 30, 2019, 10:50:45 Start Time :Dec 30, 2019, 14:29:38 End Time :--	Pending for Intervention	Batch Execution Policy	Modify Continue Delete

5.2.6 Delete a task

For better management, you can delete a task that is no longer in use.

Procedure

1. [Log on to Apsara Stack Operations.](#)
2. In the left-side navigation pane, choose **Task Management > Task Management**.
3. Optional: Enter the task name, select the task status, and configure the start time and end time of the task. Then, click **Query** to search for the task.
4. Find the task to be deleted and then click **Delete** in the **Actions** column.
5. Click **OK** in the displayed dialog box.

5.2.7 Process tasks to be intervened

If a task has a breakpoint and runs to the breakpoint, the task stops and waits for manual confirmation. The task can only continue to run after the manual confirmation.

Procedure

1. [Log on to Apsara Stack Operations.](#)
2. In the left-side navigation pane, choose **Task Management > Task Overview**.

3. In the **Tasks To Be Intervened** section, find the task to be intervened and then click **Details** in the **Actions** column.

Tasks To Be Intervened			
Task Name	Task Description	Start Time	Actions
test01	test	Dec 30, 2019, 10:59:45	Details


4. On the **Task Details** tab, check the information and then click **Continue** to continue to run the task.

5.2.8 Configure the XDB backup task

The **XDB Backup** module allows you to configure the XDB data backup without using command lines. You can configure and modify the backup task on the XDB Backup page to regularly back up platform data and back up data in real time.

Procedure

1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **Task Management > Common Tasks > XDB Backup**.
3. On the **XDB Backup** page, configure the XDB backup task information.

Configuration	Description
Task Name	The name of the XDB backup task. By default, the name is xdbBackup and cannot be modified.
Task Description	The description of the XDB backup task.
Target Group	<p>Required. The target of the XDB backup task. You can configure the target group in the following ways:</p> <ul style="list-style-type: none"> • Select from the drop-down list by product > cluster > service > server role > virtual machine (VM) or physical machine. • Select a product. Enter the VM or physical machine in the field and then press Enter. You can enter multiple VMs or physical machines in sequence. • Click the  button next to Target Group. In the displayed dialog box, enter the target group, with one VM or physical machine in one line, and then click OK.

Configuration	Description
Execution Batch	<p data-bbox="660 284 1406 371">Optional. This option appears after you enter the target group.</p> <p data-bbox="660 407 1374 495">You can select the following options as the Execution Batch.</p> <ul data-bbox="660 524 887 557" style="list-style-type: none"> <li data-bbox="660 524 887 557">• Default Order <p data-bbox="699 591 1414 891">If the number of machines is equal to or less than 10 , the machines are allocated to different batches by default, with one machine in batch 1, one machine in batch 2, two machines in batch 3, three machines in batch 4, and the other machines in batch 5. You can adjust the batch for machines as needed.</p> <p data-bbox="699 925 1433 1330">If the number of machines is more than 10, the machines are allocated to different batches by default , with one machine in batch 1, three machines in batch 2, five machines in batch 3, $N/3-1$ (an integer) machines in batch 4, $N/3-1$ (an integer) machines in batch 5, until all of the machines are allocated. Where , N is the total number of servers in the cluster. You can adjust the batch for machines as needed.</p> <ul data-bbox="660 1350 1433 1464" style="list-style-type: none"> <li data-bbox="660 1350 1433 1464">• Single-Machine Order: By default, each batch has one machine. You can adjust the batch for machines as needed. <p data-bbox="660 1498 1425 1850">If the execution batch is not selected, the Execution Batch switch is turned off by default, and Target Group is displayed in the Target Group column in the task list of the Task Management > Task Management page. If you select and save the execution batch, the Execution Batch switch is turned on automatically, and Batch Execution Policy is displayed in the Target Group column.</p>

Configuration	Description
Execution Method	<p>If you turn on the Execution Batch switch, the Execution Method can only be Manual Execution and cannot be selected.</p> <p>If the Execution Batch switch is not turned on, you can select one of the following execution methods:</p> <ul style="list-style-type: none"> • Manual Execution: You must manually start the task. With this option selected, you must click Start in the Actions column to run the task after the task is created. • Scheduled Execution: Select the execution time. The task automatically runs when the time is reached. • Regular Execution: Select the interval and execution times to run the task. The task runs again if the execution condition is met. • Advanced: Enter the crontab expression to configure the command, which allows the task to run periodically. <p>For example, <code>0 20 20 * * ?</code> indicates that the task runs at 20:20 every day.</p>
Execution Scripts	By default, the system automatically loads the XDB backup script.

The screenshot shows the 'XDB Backup' configuration page. It has a dark theme. At the top, there's a header 'XDB Backup'. Below it, there are two input fields: 'Task Name' with the value 'xdbBackup' and 'Task Description'. Under 'Task Description', there's a link icon. Below these is a 'Target Group' dropdown menu showing 'jianji'. Then, there's an 'Execution Batch' section with a toggle switch and two radio buttons: 'Default Order' (selected) and 'Single-Machine Order'. Below that is an 'Execution Method' dropdown menu showing 'Manual Execution'. At the bottom, there's an 'Execution Scripts' section with a table showing a script named 'xdb-backup-start.sh'. A 'Create' button is located at the bottom right corner.

4. Then, click **Create**.

You can view the created XDB backup task in the task list of the **Task Management > Task Management** page. The system automatically runs the XDB backup task when the

task execution condition is met. If **Manual Execution** is selected as the **Execution Method** of the XDB backup task, start the backup task based on the procedures in [Start a task](#).

**Note:**

After the XDB backup task is created, you can modify the information of the backup task by clicking **Modify** at the bottom of the **XDB Backup** page and configuring the XDB backup task again.

After the XDB backup task runs, operations engineers can view the backup file of each instance under the /alidata/xdb-backup/instance name directory on the backup server. The backup file name is in the format of instance name-timestamp (specific to day).tar. At the same time, the temporary backup information under the /alidata/xdb-backup-tmp directory of the temporary backup folder is deleted automatically.

5.3 Apsara Infrastructure Management Framework

5.3.1 Old version

5.3.1.1 What is Apsara Infrastructure Management Framework?

This topic describes what Apsara Infrastructure Management Framework is from the aspects of core functions and basic concepts.

5.3.1.1.1 Overview

Apsara Infrastructure Management Framework is a distributed data center management system, which manages applications on clusters containing multiple machines and provides the basic functions such as deployment, upgrade, expansion, contraction, and configuration changes.

Apsara Infrastructure Management Framework also supports monitoring data and analyzing reports, which facilitates users to perform one-stop Operation & Maintenance (O&M) control. Based on the Apsara Infrastructure Management Framework services, automated O&M is implemented in the large-scale distributed environment, which greatly improves the operations efficiency and enhances the system availability.

Apsara Infrastructure Management Framework is mainly composed of TianjiMaster and TianjiClient. Apsara Infrastructure Management Framework installs TianjiClient as the agent on machines it manages. Then, TianjiMaster accepts and issues the upper-layer instructio

ns to TianjiClient for execution. In the upper layer, Apsara Infrastructure Management Framework is divided into different components based on different functions, and then provides API server and portal for external use.

Core functions

- Network initialization in data centers
- Server installation and maintenance process management
- Deployment, expansion, and upgrade of cloud products
- Configuration management of cloud products
- Automatic application for cloud product resources
- Automatic repair of software and hardware faults
- Basic monitoring and business monitoring of software and hardware

5.3.1.1.2 Basic concepts

Before using Apsara Infrastructure Management Framework, you must know the following basic concepts for a better understanding.

project

A collection of clusters, which provides service capabilities for external entities.

cluster

A collection of physical machines, which logically provides services and is used to deploy project software.

- A cluster can only belong to one project.
- Multiple services can be deployed on a cluster.

service

A set of software, which provides relatively independent functions. A service is composed of one or more server roles and can be deployed on multiple clusters to form multiple sets of services and provide the corresponding service capabilities. For example, Apsara Distributed File System, Job Scheduler, and Apsara Name Service and Distributed Lock Synchronization System are all services.

service instance

A service that is deployed on a cluster.

server role

One or more indivisible deployment units into which a service can be divided based on functions. A server role is composed of one or more specific applications. If a service is deployed on a cluster, all the server roles of the service must be deployed to machines of this cluster. Multiple server roles, such as PanguMaster and TianjiClient, can be deployed on the same server.

server role instance

A server role that is deployed on a machine. A server role can be deployed on multiple machines.

application

Applications correspond to each process-level service component in a server role and each application works independently. The application is the minimum unit for deployment and upgrade in Apsara Infrastructure Management Framework, and can be deployed to each machine. Generally, an application is an executable software or Docker container.

If a server role is deployed on a machine, all applications in the server role must be deployed to this machine.

rolling

Each time when a user updates configurations, Apsara Infrastructure Management Framework upgrades services and modifies the cluster configurations based on the updated configurations. This process is called rolling.

service configuration template

Some configurations are the same when services are deployed on clusters. A service configuration template can be created to quickly write the same configurations to different clusters. The service configuration template is basically used for large-scale deployment and upgrade.

associated service template

A template.conf file that exists in the configurations. This file declares the service configuration template and its version, of which the configuration is used by the service instance.

final status

If a cluster is in this status, all hardware and software on each of its machines are normal and all software are in the target version.

dependency

The dependency between server roles in a service defines that server roles with dependencies run tasks or are upgraded based on the dependency order. For example, if A depends on B, B is upgraded first. A starts to be downloaded after B is downloaded successfully, and upgraded after B is successfully upgraded. (By default, the dependency does not take effect for configuration upgrade.)

upgrade

A way of aligning the current status with the final status of a service. After a user submits the version change, Apsara Infrastructure Management Framework upgrades the service version to the target version. With the server role as the processing unit, upgrade aims to update the versions of all machines to the target version.

At the beginning, the final status and current status of the cluster are the same. When a user submits the change, the final status is changed, whereas the current status is not. A rolling task is generated and has the final status as the target version. During the upgrade, the current status is continuously approximating to the final status. Finally, the final status and the current status are the same when the upgrade is finished.

5.3.1.2 Log on to Apsara Infrastructure Management Framework

This topic describes how to log on to Apsara Infrastructure Management Framework.


Prerequisites

- ASO access address in the format of `http://region-id.aso.intranet-domain-id.com`.
- Google Chrome browser (recommended).

Procedure

1. Open the browser.

2. Enter the ASO access address `http://region-id.aso.intranet-domain-id.com` in the address bar and then press Enter.

The image shows a dark-themed login interface. At the top, the text "Log On" is displayed in a light blue font. Below this, there are two input fields. The first field is preceded by a user icon and the placeholder text "Enter a user name". The second field is preceded by a lock icon and the placeholder text "Enter the password". At the bottom of the form is a large blue button with the text "Log On" in white.**Note:**

You can select the language from the drop-down list in the upper-right corner to change the language of ASO.

3. Enter the correct username and password.

**Note:**

Obtain the username and password used to log on to ASO from the deployment personnel or the administrator.

- The system has three default users:
 - Security officer: manages other users or roles.
 - Auditor officer: views audit logs.
 - System administrator: used for other functions except those of the security officer and auditor officer.
- You must modify the password of your username as instructed when you log on to ASO for the first time. To improve security, the password must be 10-20 characters long and can contain English uppercase/lowercase letters (A-Z or a-z), numbers (0-9), and special characters, such as exclamation points (!), at signs (@), number signs (#), dollar signs (\$), and percent signs (%), which meets the minimum complexity requirements.

4. Click **Log On** to log on to ASO.

5. In the left-side navigation pane, select **Products**.

6. In the product list, select **Apsara Infrastructure Management Framework**.

5.3.1.3 Web page introduction


Before performing Operation & Maintenance (O&M) operations on Apsara Infrastructure Management Framework, you must have a general understanding of the Apsara Infrastructure Management Framework page.

5.3.1.3.1 Introduction on the home page

After you log on to Apsara Infrastructure Management Framework, the home page appears. This topic allows you to get a general understanding of the basic operations and functions of Apsara Infrastructure Management Framework.

[Log on to Apsara Infrastructure Management Framework](#). The home page appears, as shown in [Figure 5-1: Home page of Apsara Infrastructure Management Framework](#).




Figure 5-1: Home page of Apsara Infrastructure Management Framework



For more information about the descriptions of functional areas on the home page, see [Table 5-1: Descriptions of functional areas](#).

Table 5-1: Descriptions of functional areas

Area		Description
1	Top navigation bar	<ul style="list-style-type: none">• Operations: the quick entrance of Operations & Maintenance (O&M) operations, which allows operations engineers to quickly find the corresponding operations and operation objects. This menu consists of the following sections:<ul style="list-style-type: none">- Cluster Operations: performs O&M operations on and manages clusters with the project permissions, such as viewing the cluster status.- Service Operations: manages services with the service permissions, such as viewing the service list information.- Machine Operations: maintains and manages all the machines in Apsara Infrastructure Management Framework, such as viewing the machine status.• Tasks: A rolling task is generated after you modify the configurations in the system. In this menu, you can view running tasks, history tasks, and the deployment summary of clusters, services, and server roles in all projects.• Reports: displays the monitoring data in tables and provides the function of searching for different reports.• Monitoring: effectively monitors metrics in the process of system operation and sends alert notifications for abnormal conditions. This menu includes the functions of displaying alert status, modifying alert rules, and searching for the alert history.

Area	Description
<p>2</p> <p>Function buttons in the upper-right corner</p>	<ul style="list-style-type: none"> : <ul style="list-style-type: none"> - TJDB Synchronization Time: the generated time of the data that is displayed on the current page. - Final Status Computing Time: the computing time of the final-status data that is displayed on the current page. <p>After data is generated, the system processes the data at maximum speed. As an asynchronous system, Apsara Infrastructure Management Framework has some latency. The time helps explain why the current data results are generated and determine whether the current system has a problem.</p> : In the English environment, click this drop-down list to switch to another language. : The logon account information. Click this drop-down list and select Logout to log out of Apsara Infrastructure Management Framework.
<p>3</p> <p>Left-side navigation pane</p>	<p>In the left-side navigation pane, you can directly view the logical structure of the Apsara Infrastructure Management Framework model.</p> <p>You can view the corresponding detailed data analysis and operations by selecting different levels of nodes in the left-side navigation pane. For more information, see Introduction on the left-side navigation pane.</p>

Area		Description
4	Home page	<p>Displays the summary of related tasks or information as follows:</p> <ul style="list-style-type: none"> • Upgrade Task Summary: the numbers and proportions of running, rolling back, and paused upgrade tasks. • Cluster Summary: the numbers of machines, error alerts, operating system errors, and hardware errors for different clusters. • Error Summary: the metrics for the rate of abnormal machines and the rate of abnormal server role instances. • Most-used Reports: links of the most commonly used statistics reports, which facilitates you to view the report information.
5	Button used to collapse/expand the left-side navigation pane	<p>If you are not required to use the left-side navigation pane when performing O&M operations, click this button to collapse the left-side navigation pane and increase the space of the content area.</p>



5.3.1.3.2 Introduction on the left-side navigation pane


The left-side navigation pane has three common tabs: **C** (cluster), **S** (service), and **R** (report). With some operations, you can view the related information quickly.

Cluster

Fuzzy search is supported to search for the clusters in a project, and you can view the cluster status, cluster operations information, service final status, and logs.

In the left-side navigation pane, click the **C** tab. Then, you can:

- Enter the cluster name in the search box to search for the cluster quickly. Fuzzy search is supported.
- Select a project from the **Project** drop-down list to display all the clusters in the project.
- Move the pointer over  at the right of a cluster and then perform operations on the cluster as instructed.
- Click a cluster and all the machines and services in this cluster are displayed in the lower-left corner. Move the pointer over  at the right of a machine or service and then perform operations on the machine or service as instructed.



- Click the **Machine** tab in the lower-left corner. Double-click a machine to view all the server roles in the machine. Double-click a server role to view the applications and then double-click an application to view the log files.
- Click the **Service** tab in the lower-left corner. Double-click a service to view all the server roles in the service. Double-click a server role to view the machines, double-click a machine to view the applications, and double-click an application to view the log files.
- Double-click a log file. Move the pointer over  at the right of the log file and then select **Download** to download the log file.

Move the pointer over a log file and then click **View** at the right of the log file to view the log details based on time. On the **Log Viewer** page, enter the keyword to search for logs.

Service

Fuzzy search is supported to search for services and you can view services and service instances.

In the left-side navigation pane, click the **S** tab. Then, you can:

- Enter the service name in the search box to search for the service quickly. Fuzzy search is supported.
- Move the pointer over  at the right of a service and then perform operations on the service as instructed.
- Click a service and all the service instances in this service are displayed in the lower-left corner. Move the pointer over  at the right of a service instance and then perform operations on the service instance as instructed.

Report

Fuzzy search is supported to search for reports and you can view the report details.

In the left-side navigation pane, click the **R** tab. Then, you can:

- Enter the report name in the search box to search for the report quickly. Fuzzy search is supported.
- Click **All Reports** or **Favorites** to display groups of different categories in the lower-left corner. Double-click a group to view all the reports in this group. Double-click a report to view the report details on the right pane.

5.3.1.4 Cluster operations

This topic describes the actions about cluster operations.

5.3.1.4.1 View cluster configurations

By viewing the cluster configurations, you can view the basic information, deployment plan, and configurations of a cluster.

Procedure

1. [Log on to Apsara Infrastructure Management Framework](#).
2. In the top navigation bar, choose **Operations > Cluster Operations**.

The **Cluster Operations** page displays the following information:

- **Cluster**

The cluster name. Click the cluster name to go to the [Cluster Dashboard](#) page.

- **Scale-Out/Scale-In**

The number of machines or server roles that are scaled out or in. Click the link to go to the [Cluster Operation and Maintenance Center](#) page.

- **Abnormal Machine Count**

The statistics of machines whose status is not Good in the cluster. Click the link to go to the [Cluster Operation and Maintenance Center](#) page.

- **Final Status of Normal Machines**

Displays whether the cluster reaches the final status. Select **Clusters Not Final** to display clusters that do not reach the final status. Click the link to go to the [Service Final Status Query](#) page.

- **Rolling**

Displays whether the cluster has a running rolling task. Select **Rolling Tasks** to display clusters that have rolling tasks. Click the link to go to the [Rolling Task](#) page.

3. Select a project from the **Project** drop-down list and/or enter the cluster name in the **Cluster** field to search for clusters.

4. Find the cluster whose configurations you are about to view and then click **Cluster Configuration** in the **Actions** column. The **Cluster Configuration** page appears.

For more information about the **Cluster Configuration** page, see [Table 5-2: Cluster configurations](#).

Table 5-2: Cluster configurations

Category	Item	Description
Basic Information	Cluster	The cluster name.
	Project	The project to which the cluster belongs.
	Clone Switch	<ul style="list-style-type: none"> • Mock Clone: The system is not cloned when a machine is added to the cluster. • Real Clone: The system is cloned when a machine is added to the cluster.
	Machines	The number of machines in the cluster. Click View Clustering Machines to view the machine list.
	Security Verification	The access control among processes. Generally, the non-production environment uses the default configurations and does not perform the verification. In other cases, customize the configurations based on actual requirements to enable or disable the verification.
	Cluster Type	<ul style="list-style-type: none"> • RDS • NETFRAME • T4: a special type that is required by the mixed deployment of e-commerce. • Default: other conditions.
Deployment Plan	Service	The service deployed in the cluster.
	Dependency Service	The service that the current service depends on.


Category	Item	Description
Service Information	Service Information	Select a service from the Service Information drop-down list and then the configurations of this service are displayed.
	Service Template	The template used by the service.
	Monitoring Template	The monitoring template used by the service.
	Machine Mappings	The machines included in the server role of the service.
	Software Version	The software version of the server role in the service.
	Availability Configuration	The availability configuration percentage of the server role in the service.
	Deployment Plan	The deployment plan of the server role in the service.
	Configuration Information	The configuration file used in the service.
	Role Attribute	Server roles and the corresponding parameters.

5. Click **Operation Logs** in the upper-right corner to view the release changes. For more information, see [View operation logs](#).

5.3.1.4.2 View the cluster dashboard

The cluster dashboard allows you to view the basic information and related statistics of a cluster.

Procedure

1. [Log on to Apsara Infrastructure Management Framework](#).
2. You have two ways to go to the **Cluster Dashboard** page:
 - In the left-side navigation pane, click the **C** tab. Move the pointer over  at the right of a cluster and then select **Dashboard**.
 - In the top navigation bar, choose **Operations > Cluster Operations**. On the **Cluster Operations** page, click the cluster name.

3. On the **Cluster Dashboard** page, you can view the cluster information, including the basic information, final status information, rolling job information, dependencies, resource information, virtual machines, and monitoring information. For more information about the descriptions, see the following table.

Item	Description
Basic Cluster Information	<p>Displays the basic information of the cluster as follows:</p> <ul style="list-style-type: none"> • Project Name: the project name. • Cluster Name: the cluster name. • IDC: the data center to which the cluster belongs. • Final Status Version: the latest version of the cluster. • Cluster in Final Status: whether the cluster reaches the final status. • Machines Not In Final Status: the number of machines that do not reach the final status in the cluster when the cluster does not reach the final status. • Real/Pseudo Clone: whether to clone the system when a machine is added to the cluster. • Expected Machines: the number of expected machines in the cluster. • Actual Machines: the number of machines in the current environment. • Machines Not Good: the number of machines whose status is not Good in the cluster. • Actual Services: the number of services that are actually deployed in the cluster. • Actual Server Roles: the number of server roles that are actually deployed in the cluster. • Cluster Status: whether the cluster is starting or shutting down machines.
Machine Status Overview	The statistical chart of the machine status in the cluster.
Machines in Final Status	The numbers of machines that reach the final status and those that do not reach the final status in each service of the cluster.
Load-System	The system load chart of the cluster.
CPU-System	The CPU load chart.
Mem-System	The memory load chart.
Disk_usage-System	The statistical table of the disk usage.

Item	Description
Traffic-System	The system traffic chart.
TCP State-system	The TCP request status chart.
TCP Retrans-System	The chart of TCP retransmission amount.
Disk_IO-System	The statistical table of the disk input and output.
Service Instances	<p>Displays the service instances deployed in the cluster and the related final status information.</p> <ul style="list-style-type: none"> • Service Instance: the service instance deployed in the cluster. • Final Status: whether the service instance reaches the final status. • Expected Server Roles: the number of server roles that the service instance expects to deploy. • Server Roles In Final Status: the number of server roles that reach the final status in the service instance. • Server Roles Going Offline: the number of server roles that are going offline in the service instance. • Actions: Click Details to go to the Service Instance Information Dashboard page. For more information about the service instance dashboard, see View the service instance dashboard.
Upgrade Tasks	<p>Displays the upgrade tasks related to the cluster.</p> <ul style="list-style-type: none"> • Cluster Name: the name of the upgrade cluster. • Type: the type of the upgrade task. The options include app (version upgrade) and config (configuration change). • Git Version: the change version to which the upgrade task belongs. • Description: the description about the change. • Rolling Result: the result of the upgrade task. • Submitted By: the person who submits the change. • Submitted At: the time when the change is submitted. • Start Time: the time to start the rolling. • End Time: the time to finish the upgrade. • Time Used: the time used for the upgrade. • Actions: Click Details to go to the Rolling Task page. For more information about the rolling task, see View rolling tasks.


Item	Description
Cluster Resource Request Status	<ul style="list-style-type: none"> • Version: the resource request version. • Msg: the exception message. • Begintime: the start time of the resource request analysis. • Endtime: the end time of the resource request analysis. • Build Status: the build status of resources. • Resource Process Status: the resource request status in the version.
Cluster Resource	<ul style="list-style-type: none"> • Service: the service name. • Server Role: the server role name. • App: the application of the server role. • Name: the resource name. • Type: the resource type. • Status: the resource request status. • Error Msg: the exception message. • Parameters: the resource parameters. • Result: the resource request result. • Res: the resource ID. • Reprocess Status: the status of interaction with Business Foundation System during the VIP resource request. • Reprocess Msg: the exception message of interaction with Business Foundation System during the VIP resource request. • Reprocess Result: the result of interaction with Business Foundation System during the VIP resource request. • Refer Version List: the version that uses the resource.
VM Mappings	<p>The information of virtual machines in the cluster. Data is available only when virtual machines are deployed in the cluster.</p> <ul style="list-style-type: none"> • VM: the hostname of the virtual machine. • Currently Deployed On: the hostname of the physical machine where the virtual machine is currently deployed. • Target Deployed On: the hostname of the physical machine where the virtual machine is expected to be deployed.

Item	Description
Service Dependencies	<p>The dependencies of service instances and server roles in the cluster, and the final status information of the dependent service or server role.</p> <ul style="list-style-type: none"> • Service: the service name. • Server Role: the server role name. • Dependent Service: the service on which the server role depends. • Dependent Server Role: the server role on which the server role depends. • Dependent Cluster: the cluster to which the dependent server role belongs. • Dependency in Final Status: whether the dependent server role reaches the final status.

5.3.1.4.3 View the cluster operation and maintenance center


The cluster operation and maintenance center allows you to view the status or statistics of services or machines in the cluster.

Procedure

1. [Log on to Apsara Infrastructure Management Framework.](#)
2. You have three ways to go to the **Cluster Operation and Maintenance Center** page:
 - In the left-side navigation pane, click the **C** tab. Move the pointer over  at the right of a cluster and then select **Cluster Operation and Maintenance Center**.
 - In the top navigation bar, choose **Operations > Cluster Operations**. On the **Cluster Operations** page, choose **Monitoring > Cluster Operation and Maintenance Center** in the **Actions** column at the right of a cluster.
 - In the top navigation bar, choose **Operations > Cluster Operations**. On the **Cluster Operations** page, click a cluster name. On the **Cluster Dashboard** page, choose **Operations Menu > Cluster Operation and Maintenance Center**.

3. View the information on the **Cluster Operation and Maintenance Center** page.

Item	Description
SR not in Final Status	<p>Displays all the server roles that do not reach the final status in the cluster.</p> <p>Click the number to expand a server role list, and click a server role in the list to display the information of machines included in the server role.</p>
Running Tasks	<p>Displays whether the cluster has running rolling tasks.</p> <p>Click Rolling to go to the Rolling Task page. For more information about the rolling task, see View rolling tasks.</p>
Head Version Submitted At	<p>The time when the head version is submitted.</p> <p>Click the time to view the submission details.</p>
Head Version Analysis	<p>The head version analysis is the process that Apsara Infrastructure Management Framework detects the latest cluster version and parses the version to detailed change contents. The head version analysis has the following statuses:</p> <ul style="list-style-type: none"> • Preparing: No new version is available now. • Waiting: The latest version is found. The analysis module has not started up yet. • Doing: The module is analyzing the application that requires change. • done: The head version analysis is successfully completed. • Failed: The head version analysis failed. The change contents cannot be parsed. <p>If the status is not done, Apsara Infrastructure Management Framework cannot detect the change contents of server roles in the latest version.</p> <p>Click the status to view the relevant information.</p>
Service	Select a service deployed in the cluster from the drop-down list.

Item	Description
Server Role	<p>Select a server role of a service in the cluster from the drop-down list.</p> <div>  Note: After you select the service and server role, the information of machines related to the service or server role is displayed in the list. </div>
Total Machines	The total number of machines in the cluster, or the total number of machines included in a specific server role of a specific service .
Scale-in/Scale-out	The number of machines or server roles that are scaled in or out.
Abnormal Machines	<p>The number of abnormal machines that encounter each type of the following faults.</p> <ul style="list-style-type: none"> • Ping Failed: A ping_monitor error is reported, and TianjiMaster cannot successfully ping the machine. • No Heartbeat: TianjiClient on the machine does not regularly report data to indicate the status of this machine, which may be caused by the TianjiClient problem or network problem. • Status Error: The machine has an error reported by the monitor or a fault of the critical or fatal level. Check the alert information and accordingly solve the issue.
Abnormal Services	<p>The number of machines with abnormal services. To determine if a service reaches the final status, see the following rules:</p> <ul style="list-style-type: none"> • The server role on the machine is in the GOOD status. • Each application of the server role on the machine must keep the actual version the same as the head version. • Before the Image Builder builds an application of the head version, Apsara Infrastructure Management Framework cannot determine the value of the head version and the service final status is unknown. This process is called the change preparation process. The service final status cannot be determined during the preparation process or upon a preparation failure.

Item	Description
Machines	<p>Displays all the machines in the cluster or the machines included in a specific server role of a specific service.</p> <ul style="list-style-type: none"> Machine search: Click the search box to enter the machine in the displayed dialog box. Fuzzy or batch search is supported. Click the machine name to view the physical information of the machine in the displayed Machine Information dialog box. Click DashBoard to go to the Machine Details page. For more information about the machine details, see View the machine dashboard. Move the pointer over the blank area in the Final Status column or the Final SR Status column and then click Details to view the machine status, system service information, server role status on the machine, and exception message. If no service or server role is selected from the drop-down list, move the pointer over the blank area in the Running Status column and then click Details to view the running status information or exception message of the machine. <p>If a service and a server role are selected from the corresponding drop-down lists, move the pointer over the blank area in the SR Running Status column and then click Details to view the running status information or exception message of the server role on the machine.</p> <ul style="list-style-type: none"> Click Error, Warning, or Good in the Monitoring Statistics column to view the monitored items of machines and monitored items of server roles. Click Terminal in the Actions column to log on to the machine and perform related operations. Click Machine Operation in the Actions column to restart, out-of-band restart, or clone the machine again.


5.3.1.4.4 View the service final status

The **Service Final Status Query** page allows you to view if a service in a cluster reaches the final status and the final status information.

Procedure


1. [Log on to Apsara Infrastructure Management Framework](#).

2. You have two ways to go to the **Service Final Status Query** page:

- In the left-side navigation pane, click the **C** tab. Move the pointer over  at the right of a cluster and then choose **Monitoring > Service Final Status Query**.
- In the top navigation bar, choose **Operations > Cluster Operations**. On the **Cluster Operations** page, choose **Monitoring > Service Final Status Query** in the **Actions** column at the right of a cluster.

3. View the information on the **Service Final Status Query** page.


Item	Description
Project Name	The name of the project to which the cluster belongs.
Cluster Name	The cluster name.
Head Version Submitted At	The time when the head version is submitted.
Head Version Analysis	<p>The head version analysis is the process that Apsara Infrastructure Management Framework detects the latest cluster version and parses the version to detailed change contents. The head version analysis has the following statuses:</p> <ul style="list-style-type: none"> • Preparing: No new version is available now. • Waiting: The latest version is found. The analysis module has not started up yet. • Doing: The module is analyzing the application that requires change. • done: The head version analysis is successfully completed. • Failed: The head version analysis failed. The change contents cannot be parsed. <p>If the status is not done, Apsara Infrastructure Management Framework cannot detect the change contents of server roles in the latest version.</p>
Cluster Rolling Status	Displays the information of the current rolling task in the cluster, if any. The rolling task may not be of the head version.

Item	Description
Cluster Machine Final Status Statistics	The status of all machines in the cluster. Click View Details to go to the Cluster Operation and Maintenance Center page and view the detailed information of all machines. For more information about the cluster operation and maintenance center, see View the cluster operation and maintenance center .
Final Status of Cluster SR Version	<p>The final status of cluster service version.</p> <div>  Note: Take statistics of services that do not reach the final status, which is caused by version inconsistency or status exceptions. If services do not reach the final status because of machine problems, go to Cluster Machine Final Status Statistics to view the statistics. </div>
Final Status of SR Version	The number of machines that do not reach the final status when a server role has tasks.

5.3.1.4.5 View operation logs

By viewing operation logs, you can obtain the differences between different Git versions.

Procedure

1. [Log on to Apsara Infrastructure Management Framework](#).
2. You have two ways to go to the **Cluster Operation Logs** page:
 - In the left-side navigation pane, click the **C** tab. Move the pointer over  at the right of a cluster and then choose **Monitoring > Operation Logs**.
 - In the top navigation bar, choose **Operations > Cluster Operations**. On the **Cluster Operations** page, choose **Monitoring > Operation Logs** in the **Actions** column at the right of a cluster.
3. On the **Cluster Operation Logs** page, click **Refresh**. View the Git version, description, submitter, submitted time, and task status.

4. Optional: Complete the following steps to view the differences between versions on the **Cluster Operation Logs** page.

- a) Find the log in the operation log list and then click **View Release Changes** in the **Actions** column.
- b) On the **Version Difference** page, complete the following configurations:
 - **Select Base Version:** Select a base version.
 - **Configuration Type:** Select **Extended Configuration** or **Cluster Configuration**.
Extended Configuration displays the configuration differences after the configuration on the cluster is combined with the configuration in the template.
Cluster Configuration displays the configuration differences on the cluster.
- c) Click **Obtain Difference**.
 The differential file list is displayed.
- d) Click each differential file to view the detailed differences.

5.3.1.5 Service operations

This topic describes the actions about service operations.

5.3.1.5.1 View the service list

The service list allows you to view the list of all services and the related information.

Procedure

1. [Log on to Apsara Infrastructure Management Framework](#).
2. In the top navigation bar, choose **Operations > Service Operations**.
3. View the information on the **Service Operations** page.


Item	Description
Service	The service name.
Service Instances	The number of service instances in the service.
Service Configuration Templates	The number of service configuration templates.
Monitoring Templates	The number of monitoring templates.
Service Schemas	The number of service configuration validation templates.

Item	Description
Actions	Click Management to view the service instances, service templates, monitoring templates, monitoring instances, service schemas, and detection scripts.

5.3.1.5.2 View the service instance dashboard

The service instance dashboard allows you to view the basic information and statistics of a service instance.

Procedure

1. [Log on to Apsara Infrastructure Management Framework](#).
2. In the left-side navigation pane, click the **S** tab.
3. Enter the service name in the search box. Services that meet the search condition are displayed.
4. Click a service name and then service instances in the service are displayed in the lower-left corner.
5. Move the pointer over  at the right of a service instance and then select **Dashboard**.

6. View the information on the **Service Instance Information Dashboard** page.


Item	Description
Service Instance Summary	<p>Displays the basic information of the service instance as follows:</p> <ul style="list-style-type: none"> • Cluster Name: the name of the cluster to which the service instance belongs. • Service Name: the name of the service to which the service instance belongs. • Actual Machines: the number of machines in the current environment. • Expected Machines: the number of machines that the service instance expects. • Target Total Server Roles: the number of server roles that the service instance expects. • Actual Server Roles: the number of server roles in the current environment. • Template Name: the name of the service template used by the service instance. • Template Version: the version of the service template used by the service instance. • Schema: the name of the service schema used by the service instance. • Monitoring System Template: the name of the monitoring system template used by the service instance.
Server Role Statuses	The statistical chart of the current status of server roles in the service instance.
Machine Statuses for Server Roles	The status statistics of machines where server roles are located.
Service Monitoring Information	<ul style="list-style-type: none"> • Monitored Item: the name of the monitored item. • Level: the level of the monitored item. • Description: the description of the monitored contents. • Updated At: the time when the data is updated.

Item	Description
Service Alert Status	<ul style="list-style-type: none"> • Alert Name • Instance Information • Alert Start • Alert End • Alert Duration • Severity Level • Occurrences: the number of times the alert is triggered.
Server Role List	<ul style="list-style-type: none"> • Server Role • Current Status • Expected Machines • Machines In Final Status • Machines Going Offline • Rolling Task Status • Time Used: the time used for running the rolling task. • Actions: Click Details to go to the Server Role Dashboard page.
Service Alert History	<ul style="list-style-type: none"> • Alert Name • Alert Time • Instance Information • Severity Level • Contact Group
Service Dependencies	<p>The dependencies of service instances and server roles in the service instance, and the final status information of the dependent service or server role.</p> <ul style="list-style-type: none"> • Server Role: the server role name. • Dependent Service: the service on which the server role depends. • Dependent Server Role: the server role on which the server role depends. • Dependent Cluster: the cluster to which the dependent server role belongs. • Dependency in Final Status: whether the dependent server role reaches the final status.

5.3.1.5.3 View the server role dashboard

The server role dashboard allows you to view the statistics of a server role.

Procedure

1. [Log on to Apsara Infrastructure Management Framework.](#)
2. In the left-side navigation pane, click the **S** tab.
3. Enter the service name in the search box. Services that meet the search condition are displayed.
4. Click a service name and then service instances in the service are displayed in the lower-left corner.
5. Move the pointer over  at the right of a service instance and then select **Dashboard**.
6. In the **Server Role List** section of the **Service Instance Information Dashboard** page, click **Details** in the **Actions** column.
7. View the information on the **Server Role Dashboard** page.

Item	Description
Server Role Summary	<p>Displays the basic information of the server role as follows:</p> <ul style="list-style-type: none"> • Project Name: the name of the project to which the server role belongs. • Cluster Name: the name of the cluster to which the server role belongs. • Service Instance: the name of the service instance to which the server role belongs. • Server Role: the server role name. • In Final Status: whether the server role reaches the final status. • Expected Machines: the number of expected machines. • Actual Machines: the number of actual machines. • Machines Not Good: the number of machines whose status is not Good. • Machines with Role Status Not Good: the number of server roles whose status is not Good. • Machines Going Offline: the number of machines that are going offline. • Rolling: whether a running rolling task exists. • Rolling Task Status: the current status of the rolling task. • Time Used: the time used for running the rolling task.
Machine Final Status Overview	The statistical chart of the current status of the server role.

Item	Description
Server Role Monitoring Information	<ul style="list-style-type: none"> • Updated At: the time when the data is updated. • Monitored Item: the name of the monitored item. • Level: the level of the monitored item. • Description: the description of the monitored item.
Machine Information	<ul style="list-style-type: none"> • Machine Name: the hostname of the machine. • IP: the IP address of the machine. • Machine Status: the machine status. • Machine Action: the action that the machine is performing. • Server Role Status: the status of the server role. • Server Role Action: the action that the server role is performing. • Current Version: the current version of the server role on the machine. • Target Version: the expected version of the server role on the machine. • Error Message: the exception message. • Actions: <ul style="list-style-type: none"> - Click Terminal to log on to the machine and perform operations. - Click Restart to restart the server roles on the machine. - Click Details to go to the Machine Details page. For more information about the machine details, see View the machine dashboard. - Click Machine System View to go to the Machine Info Report page. For more information about the machine info report, see Machine info report. - Click Machine Operation to restart, out of band restart, or clone the machine again.
Server Role Monitoring Information of Machines	<ul style="list-style-type: none"> • Updated At: the time when the data is updated. • Machine Name: the machine name. • Monitored Item: the name of the monitored item. • Level: the level of the monitored item. • Description: the description of the monitored item.

Item	Description
VM Mappings	<p>The information of virtual machines in the cluster. Data is available only when virtual machines are deployed in the cluster.</p> <ul style="list-style-type: none"> • VM: the hostname of the virtual machine. • Currently Deployed On: the hostname of the physical machine where the virtual machine is currently deployed. • Target Deployed On: the hostname of the physical machine where the virtual machine is expected to be deployed.
Service Dependencies	<p>The dependencies of service instances and server roles in the service instance, and the final status information of the dependent service or server role.</p> <ul style="list-style-type: none"> • Dependent Service: the service on which the server role depends. • Dependent Server Role: the server role on which the server role depends. • Dependent Cluster: the cluster to which the dependent server role belongs. • Dependency in Final Status: whether the dependent server role reaches the final status.


5.3.1.6 Machine operations

This topic describes the actions about machine operations.

5.3.1.6.1 View the machine dashboard

The machine dashboard allows you to view the statistics of a machine.

Procedure

1. [Log on to Apsara Infrastructure Management Framework.](#)
2. In the left-side navigation pane, click the **C** tab.
3. On the **Machine** tab in the lower-left corner, enter the machine name in the search box.
Machines that meet the search condition are displayed.
4. Move the pointer over  at the right of a machine and then select **Dashboard**.

5. On the **Machine Details** page, view all the information of this machine. For more information, see the following table.

Item	Description
Load-System	The system load chart of the cluster.
CPU-System	The CPU load chart.
Mem-System	The memory load chart.
DISK Usage-System	The statistical table of the disk usage.
Traffic-System	The system traffic chart.
TCP State-System	The TCP request status chart.
TCP Retrans-System	The chart of TCP retransmission amount.
DISK IO-System	The statistical table of the disk input and output.
Machine Summary	<ul style="list-style-type: none"> • Project Name: the name of the project to which the machine belongs. • Cluster Name: the name of the cluster to which the machine belongs. • Machine Name: the machine name. • SN: the serial number of the machine. • IP: the IP address of the machine. • IDC: the data center of the machine. • Room: the room in the data center where the machine is located. • Rack: the rack where the machine is located. • Unit in Rack: the location of the rack. • Warranty: the warranty of the machine. • Purchase Date: the date when the machine is purchased. • Machine Status: the running status of the machine. • Status: the hardware status of the machine. • CPUs: the number of CPUs for the machine. • Disks: the disk size. • Memory: the memory size. • Manufacturer: the machine manufacturer. • Model: the machine model. • os: the operating system of the machine. • part: the disk partition.
Server Role Status of Machine	The distribution of the current status of all server roles on the machine.

Item	Description
Machine Monitoring Information	<ul style="list-style-type: none"> • Monitored Item: the name of the monitored item. • Level: the level of the monitored item. • Description: the description of the monitored contents. • Updated At: the time when the monitoring information is updated.
Machine Server Role Status	<ul style="list-style-type: none"> • Service Instance • Server Role • Server Role Status • Server Role Action • Error Message • Target Version • Current Version • Actual Version Update Time • Actions: <ul style="list-style-type: none"> - Click Details to go to the Server Role Dashboard page. For more information about the server role dashboard, see View the server role dashboard. - Click Restart to restart the server roles on the machine.
Application Status in Server Roles	<ul style="list-style-type: none"> • Application Name: the application name. • Process Number • Status: the application status. • Current Build ID: the ID of the current package version. • Target Build ID: the ID of the expected package version. • Git Version • Start Time • End Time • Interval: the interval between the time when Apsara Infrastructure Management Framework detects that the process exits and the time when Apsara Infrastructure Management Framework repairs the process. • Information Message: the normal output logs. • Error Message: the abnormal logs.

5.3.1.7 Monitoring center

You can view the alert status, alert rules, and alert history in the monitoring center.

5.3.1.7.1 Modify an alert rule

You can modify an alert rule based on the actual business requirements.

Procedure

1. [Log on to Apsara Infrastructure Management Framework.](#)
2. In the top navigation bar, choose **Operations > Service Operations**.
3. Enter the service name in the search box.
4. Find the service and then click **Management** in the **Actions** column.
5. Click the **Monitoring Template** tab.
6. Find the monitoring template that you are about to edit and then click **Edit** in the **Actions** column.
7. Configure the monitoring parameters based on actual conditions.
8. Click **Save Change**.

Wait about 10 minutes. The monitoring instance is automatically deployed. If the status becomes **Successful** and the deployment time is later than the modified time of the template, the changes are successfully deployed.

5.3.1.7.2 View the status of a monitoring instance

After a monitoring instance is deployed, you can view the status of the monitoring instance.

Procedure

1. [Log on to Apsara Infrastructure Management Framework.](#)
2. In the top navigation bar, choose **Operations > Service Operations**.
3. Enter the service name in the search box.
4. Find the service and then click **Management** in the **Actions** column.
5. Click the **Monitoring Instance** tab.

In the **Status** column, view the current status of the monitoring instance.

5.3.1.7.3 View the alert status

The **Alert Status** page allows you to view the alerts generated in different services and the corresponding alert details.

Procedure

1. [Log on to Apsara Infrastructure Management Framework.](#)
2. In the top navigation bar, choose **Monitoring > Alert Status**.
3. You can configure the service name, cluster name, alert name, and/or the time range when the alert is triggered to search for alerts.
4. View the alert details on the **Alert Status** page. See the following table for the alert status descriptions.

Item	Description
Service	The service name.
Cluster	The name of the cluster where the service is located.
Instance	The name of the service instance being monitored. Click the instance to view the alert history of this instance.
Alert Status	Alerts have two statuses: Restored and Alerting .
Alert Level	Alerts have the following four levels, from high to low, according to the effect on services. <ul style="list-style-type: none">• P1• P2• P3• P4
Alert Name	The name of the generated alert. Click the alert name to view the alert rule details.
Alert Time	The time when the alert is triggered and how long the alert has lasted.
Actions	Click Show to show the data before and after the alert time.

5.3.1.7.4 View alert rules

The **Alert Rules** page allows you to view the configured alert rules.

Procedure

1. [Log on to Apsara Infrastructure Management Framework.](#)
2. In the top navigation bar, choose **Monitoring > Alert Rules**.
3. You can configure the service name, cluster name, and/or alert name to search for alert rules.

4. View the detailed alert rules on the **Alert Rules** page. See the following table for the alert rule descriptions.

Item	Description
Service	The service name.
Cluster	The name of the cluster where the service is located.
Alert Name	The name of the generated alert.
Alert Conditions	The conditions met when the alert is triggered.
Periods	The frequency (in seconds) with which an alert rule is run.
Alert Contact	The groups and members that are notified when an alert is triggered.
Status	The current status of the alert rule. <ul style="list-style-type: none">• Running: Click to stop this alert rule.• Stopped: Click to run this alert rule.

5.3.1.7.5 View the alert history

The **Alert History** page allows you to view all the history alerts generated in different services and the corresponding alert details.

Procedure

1. [Log on to Apsara Infrastructure Management Framework.](#)
2. In the top navigation bar, choose **Monitoring > Alert History**.
3. You can configure the service name, cluster name, time range, and/or period to search for alerts.
4. View the history alerts on the **Alert History** page. See the following table for the history alert descriptions.

Item	Description
Service	The name of the service to which the alert belongs.
Cluster	The name of the cluster where the service is located.
Alert Instance	The name of the resource where the alert is triggered.
Status	Alerts have two statuses: Restored and Alerting .

Item	Description
Alert Level	Alerts have the following four levels, from high to low, according to the effect on services. <ul style="list-style-type: none"> • P1 • P2 • P3 • P4
Alert Name	The name of the generated alert. Click the alert name to view the alert rule details.
Alert Time	The time when the alert is triggered.
Alert Contact	The groups and members that are notified when an alert is triggered.
Actions	Click Show to show the data before and after the alert time.

5.3.1.8 Tasks and deployment summary

This topic describes how to view rolling tasks, running tasks, history tasks, and deployment summary on Apsara Infrastructure Management Framework.

5.3.1.8.1 View rolling tasks

You can view running rolling tasks and the corresponding status.

Procedure

1. [Log on to Apsara Infrastructure Management Framework.](#)
2. In the top navigation bar, choose **Operations > Cluster Operations**.
3. Select **Rolling Tasks** to display clusters with rolling tasks.
4. In the search results, click **rolling** in the **Rolling** column.
5. On the displayed **Rolling Task** page, view the information in the **Change Task** list and **Change Details** list.

Table 5-3: Change Task list

Item	Description
Change Version	The version that triggers the change of the rolling task.
Description	The description about the change.

Item	Description
Head Version Analysis	<p>The head version analysis is the process that Apsara Infrastructure Management Framework detects the latest cluster version and parses the version to detailed change contents. The head version analysis has the following statuses:</p> <ul style="list-style-type: none"> • Preparing: No new version is available now. • Waiting: The latest version is found. The analysis module has not started up yet. • Doing: The module is analyzing the application that requires change. • done: The head version analysis is successfully completed. • Failed: The head version analysis failed. The change contents cannot be parsed. <p>If the status is not done, Apsara Infrastructure Management Framework cannot detect the change contents of server roles in the latest version.</p>
Blocked Server Role	Server roles blocked in the rolling task. Generally, server roles are blocked because of dependencies.
Submitter	The person who submits the change.
Submitted At	The time when the change is submitted.
Actions	<p>Click View Difference to go to the Version Difference page. For more information, see View operation logs.</p> <p>Click Stop to stop the rolling task.</p> <p>Click Pause to pause the rolling task.</p>

Table 5-4: Change Details list

Item	Description
Service Name	The name of the service where a change occurs.

Item	Description
Status	<p>The current status of the service. The rolling status of the service is an aggregated result, which is calculated based on the rolling status of the server role.</p> <ul style="list-style-type: none"> • succeeded: The task is successfully run. • blocked: The task is blocked. • failed: The task failed.
Server Role Status	<p>The server role status. Click > at the left of the service name to expand and display the rolling task status of each server role in the service.</p> <p>Server roles have the following statuses:</p> <ul style="list-style-type: none"> • Downloading: The task is being downloaded. • Rolling: The rolling task is running. • RollingBack: The rolling task failed and is rolling back.
Depend On	<p>The services that this service depends on or server roles that this server role depends on.</p>
Actions	<p>Click Stop to stop the change of the server role.</p> <p>Click Pause to pause the change of the server role.</p>

5.3.1.8.2 View running tasks

By viewing running tasks, you can know the information of all the running tasks.

Procedure

1. [Log on to Apsara Infrastructure Management Framework.](#)
2. In the top navigation bar, choose **Tasks > Running Tasks**.

3. You can configure the cluster name, role name, task status, task submitter, Git version, and/or the start time and end time of the task to search for running tasks.
4. Find the task that you are about to view the details and then click **View Tasks** in the **Rolling Task Status** column. The **Rolling Task** page appears. For more information about the rolling task, see [View rolling tasks](#).

5.3.1.8.3 View history tasks

You can view the historical running conditions of completed tasks.

Procedure

1. [Log on to Apsara Infrastructure Management Framework](#).
2. In the top navigation bar, choose **Tasks > History Tasks**.
3. You can configure the cluster name, Git version, task submitter, and/or the start time and end time of the task to search for history tasks.
4. Find the task that you are about to view the details and then click **Details** in the **Actions** column. The **Rolling Task** page appears. For more information about the rolling task, see [View rolling tasks](#).

5.3.1.8.4 View the deployment summary

On the **Deployment Summary** page, you can view the deployment conditions of clusters, services, and server roles in all projects on Apsara Infrastructure Management Framework.

Procedure

1. [Log on to Apsara Infrastructure Management Framework](#).

2. In the top navigation bar, choose **Tasks > Deployment Summary**.

- View the deployment status and the duration of a certain status for each project.
 - Gray: wait to be deployed. It indicates that some services of the project depend on server roles or service instances that are being deployed, and other service instances or server roles in the project have already been deployed.
 - Blue: being deployed. It indicates that the project has not reached the final status for one time yet.
 - Green: has reached the final status. It indicates that all clusters in the project have reached the final status.
 - Orange: not reaches the final status. It indicates that a server role does not reach the final status for some reason after the project reaches the final status for the first time.
- Configure the global clone switch.
 - **normal**: Clone is allowed.
 - **block**: Clone is forbidden.
- Configure the global dependency switch.
 - **normal**: All configured dependencies are checked.
 - **ignore**: The dependency is not checked.
 - **ignore_service**: None of the service-level dependencies, including the server role dependencies across services, are checked, and only the server role-level dependencies are checked.

3. Click the **Deployment Details** tab to view the deployment details.

For more information, see the following table.

Item	Description
Status Statistics	<p>The general statistics of deployment conditions, including the total number of projects that are currently available. Click each status to display the projects in the corresponding status in the list. The projects have five deployment statuses:</p> <ul style="list-style-type: none"> • Final: All the clusters in the project have reached the final status. • Deploying: The project has not reached the final status for one time yet. • Waiting: Some services of the project depend on server roles or service instances that are being deployed, and other service instances or server roles in the project have already been deployed. • Non-final: A server role does not reach the final status for some reason after the project reaches the final status for the first time. • Inspector Warning: An error is detected on service instances in the project during the inspection.
Start Time	The time when Apsara Infrastructure Management Framework starts the deployment.
Progress	The proportion of server roles that reach the final status to all the server roles in the current environment.
Deployment Status	<p>The time indicates the deployment duration for the following statuses: Final, Deploying, Waiting, and Inspector Warning.</p> <p>The time indicates the duration before the final status is reached for the Non-final status.</p> <p>Click the time to view the details.</p>

Item	Description
Deployment Progress	<p>The proportion of clusters, services, and server roles that reach the final status to the total clusters, services, and server roles in the project.</p> <p>Move the pointer over the blank area at the right of the data of roles and then click Details to view the deployment statuses of clusters, services, and server roles. The deployment statuses are indicated by icons, which are the same as those used for status statistics.</p>
Resource Application Progress	<p>Total indicates the total number of resources related to the project.</p> <ul style="list-style-type: none"> • Done: the number of resources that have been successfully applied for. • Doing: the number of resources that are being applied for and retried. The number of retries (if any) is displayed next to the number of resources. • Block: the number of resources whose applications are blocked by other resources. • Failed: the number of resources whose applications failed.
Inspector Error	The number of inspection alerts for the current project.
Monitoring Information	The number of alerts generated for the machine monitor and the machine server role monitor in the current project.
Dependency	Click the icon to view the project services that depend on other services, and the current deployment status of the services that are depended on.

5.3.1.9 Reports

The system allows you to search for and view reports based on your business needs, and add commonly used reports to your favorites.

5.3.1.9.1 View reports

The **Reports** menu allows you to view the statistical data.

Context


You can view the following reports on Apsara Infrastructure Management Framework.

- System reports: default and common reports in the system.
- All reports: includes the system reports and custom reports.




Procedure

1. [Log on to Apsara Infrastructure Management Framework.](#)

2. You can go to the report list in the following three ways:

- In the top navigation bar, choose **Reports > System Reports**.
- In the top navigation bar, choose **Reports > All Reports**.
- In the left-side navigation pane, click the **R** tab. Move the pointer over  at the right of **All Reports** and then select **View**.

See the following table for the report descriptions.

Item	Description
Report	The report name. Move the pointer over  next to Report to search for reports by report name.
Group	The group to which the report belongs. Move the pointer over  next to Group to filter reports by group name.
Status	Indicates whether the report is published.
Public	Indicates whether the report is public.
Created By	The person who creates the report.
Published At	The published time and created time of the report.
Actions	Click Add to Favorites to add this report to your favorites. Then, you can view the report by choosing Reports > Favorites in the top navigation bar or moving the pointer over  at the right of Favorites on the R tab in the left-side navigation pane and then selecting View .

3. Optional: Enter the name of the report that you are about to view in the search box.

4. Click the report name to go to the corresponding report details page.

For more information about the reports, see [Appendix](#).


5.3.1.9.2 Add a report to favorites

You can add common reports to favorites. Then, find them quickly on the **Favorites** page.

Procedure

1. [Log on to Apsara Infrastructure Management Framework.](#)

2. You can go to the report list in the following three ways:

- In the top navigation bar, choose **Reports > System Reports**.
- In the top navigation bar, choose **Reports > All Reports**.
- In the left-side navigation pane, click the **R** tab. Move the pointer over  at the right of **All Reports** and then select **View**.

3. Enter the name of the report that you are about to add to favorites in the search box.

4. At the right of the report, click **Add to Favorites** in the **Actions** column.

5. In the displayed **Add to Favorites** dialog box, enter tags for the report.

6. Click **Add to Favorites**.

5.3.1.10 Metadata operations

In this version, you can only use command lines to perform metadata operations.

5.3.1.10.1 Common parameters

Common parameters consist of the common request parameters and the common response parameters.

Common request parameters

Common request parameters are request parameters that you must use when you call each API.

Table 5-5: Parameter descriptions

Name	Type	Required	Description
Action	String	Yes	The API name. For more information about the valid values, see APIs on the control side and APIs on the deployment side .

Common response parameters

Each time you send a request to call an API, the system returns a unique identifier, regardless of whether the call is successful.

Table 5-6: Parameter descriptions

Name	Type	Required	Description
RequestID	String	Yes	The request ID. The request ID is returned, regardless of whether the API call is successful.
Code	String	No	The error code.
Message	String	No	The reason of failure , which appears when the API call fails.
Result	The type varies with the request, which is subject to the returned result of the specific API.	No	The request result , which appears when the API call is successful.

**Note:**

- If the API call is successful, RequestID is returned and the HTTP return code is 200.
- If the API call fails, RequestID, Code, and Message are returned and the HTTP return code is 4xx or 5xx.

Instance types

```
{
  "rds.mys2.small":{
    "cpu":2,
    "memory":4096,
    "disk":51200,
    "max_connections":60
  },
  "rds.mys2.mid":{
    "cpu":4,
    "memory":4096,
    "disk":51200,
    "max_connections":150
  },
  "rds.mys2.standard":{
    "cpu":6,
    "memory":4096,
    "disk":51200,
    "max_connections":300
  },
}
```



```
"rds.mys2.large":{
  "cpu":8,
  "memory":7200,
  "disk":102400,
  "max_connections":600
},
"rds.mys2.xlarge":{
  "cpu":9,
  "memory":12000,
  "disk":204800,
  "max_connections":1500
},
"rds.mys2.2xlarge":{
  "cpu":10,
  "memory":20000,
  "disk":512000,
  "max_connections":2000
}
}
```

5.3.1.10.2 Access APIs

This topic describes how to access APIs on the control side and the deployment side.


Procedure

1. [Log on to Apsara Infrastructure Management Framework.](#)
2. In the left-side navigation pane, choose **Operations > Machine Operations**.
3. Select a project or enter the cluster name or machine name to search for the corresponding machine.

4. Access APIs.

- Access an API on the control side
 - a. Find the machine that you are about to access and then click **Terminal** in the **Actions** column to log on to the machine.
 - b. In the command window, enter the following command and then press Enter to obtain the intranet-domain.

```
grep 'intranet-domain' /cloud/app/tianji/TianjiClient#/service_manager/current/conf.global/kv.json
```



- c. You can log on to the API on the control side in the following ways. Here, take **ListInstance** as an example.

- Get request

```
curl 'xdb-master.xdb.{intranet-domain}:15678? Action=ListInstance'
```

- Post request

```
curl 'xdb-master.xdb.{intranet-domain}:15678' -X POST -d '{"Action": "ListInstance"}
```

- Access an API on the deployment side
 - a. Find the machine that you are about to access and record the IP address in the Hostname column.
 - b. You can log on to the API on the deployment side in the following ways. Here, take **CheckState** as an example.

Assume that the IP address of the target machine is 127.0.0.1.

- Get request

```
curl '127.0.0.1:18765? Action=CheckState&Port=3606'
```

- Post request

```
curl '127.0.0.1:18765' -X POST -d '{"Action": "CheckState", "Port": 3606}'
```

5.3.1.10.3 APIs on the control side

5.3.1.10.3.1 DescribeInstance

Views instances.

Description

Views the detailed information of an instance.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: DescribeInstance
InstanceName	String	Yes	The instance name.

Response parameters

For more information about the common response parameters, see [Common response parameters](#).

Name	Type	Required	Description
InstanceID	Integer	Yes	The instance ID.
InstanceName	String	Yes	The instance name.
Domain	String	Yes	The domain name.
Port	Integer	Yes	The instance port.
PaxosPort	Integer	Yes	The communication port between instance nodes.
InstanceDir	String	Yes	The instance directory.
Level	String	Yes	The instance specifications.
User	String	Yes	The username.
Password	String	Yes	The password.

Name	Type	Required	Description
Config	String	No	The custom my.cnf configuration of the instance, which is in the JSON format.
LeaderIP	String	No	The IP address of the primary node.
ActionName	String	Yes	The action name.
ActionStatus	String	Yes	The action status.
Description	String	Yes	The description.
IsDeleted	Integer	No	Whether the instance is deleted. 0 indicates No and 1 indicates Yes.
NodeList	[]NodeInfo	Yes	The information of the instance nodes.

The structure of NodeInfo is as follows.

Name	Type	Required	Description
InstanceID	Integer	Yes	The instance ID.
InstanceName	String	Yes	The instance name.
IP	String	Yes	The IP address of the instance node.
NodeID	Integer	Yes	The ID of the instance node.
ActionName	String	Yes	The action name.
ActionStatus	String	Yes	The action status.
Description	String	Yes	The description.
IsDeleted	Integer	No	Whether the node is deleted. 0 indicates No and 1 indicates Yes.

Examples

Sample requests

```
curl 'xdb-master.xdb.env8c-inc.com:15678? Action=DescribeInstance&InstanceName=xdb-meta'
```

Sample responses

```
{
  "Result": {
    "ActionName": "",
    "Level": "rds.mys2.standard",
    "InstanceID": 1,
    "LeaderIP": "10.39.XX.XX",
    "Config": "{}",
    "Description": "",
    "ActionStatus": "",
    "Domain": "xdb-meta.xdb.env8c-inc.com",
    "PaxosPort": 11606,
    "InstanceName": "xdb-meta",
    "User": "xdb",
    "Password": "xdb",
    "Port": 3606,
    "IsDeleted": 0,
    "InstanceDir": "/apsarapangu/disk1/xdb/xdb_instance_3606",
    "NodeList": [
      {
        "ActionStatus": "",
        "ActionName": "",
        "Description": "",
        "InstanceID": 1,
        "IP": "10.38.XX.XX",
        "InstanceName": "xdb-meta",
        "NodeID": 1,
        "IsDeleted": 0
      },
      {
        "ActionStatus": "",
        "ActionName": "",
        "Description": "",
        "InstanceID": 1,
        "IP": "10.39.XX.XX",
        "InstanceName": "xdb-meta",
        "NodeID": 2,
        "IsDeleted": 0
      },
      {
        "ActionStatus": "",
        "ActionName": "",
        "Description": "",
        "InstanceID": 1,
        "IP": "10.39.XX.XX",
        "InstanceName": "xdb-meta",
        "NodeID": 3,
        "IsDeleted": 0
      }
    ]
  },
  "RequestID": "3CFCBA07-3D87-4A99-B8C1-E861A7D1A573"
}
```

```
}
```

5.3.1.10.3.2 ListInstance

Lists instances.

Description

Lists the basic information of instances.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: ListInstance

Response parameters

For more information about the common response parameters, see [Common response parameters](#).

Name	Type	Required	Description
InstanceNames	String	Yes	The list of instance names.

Examples

Sample requests

```
curl 'xdb-master.xdb.env8c-inc.com:15678? Action=ListInstance'
```

Sample responses

```
{
  "Result": {
    "InstanceNames": [
      "xdb-meta",
      "xdb-instance-1",
      "xdb-instance-2",
      "xdb-instance-3"
    ]
  },
  "RequestID": "A921B8C7-C833-417C-B46A-E0CE129EBE48"
}
```

```
}
```

5.3.1.10.3 CreateInstance

Creates an instance.

Description

Creates an instance. This is an asynchronous task. You can view the task result by calling the DescribeTaskProgress API based on the RequestID in the responses.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: CreateInstance
InstanceName	String	Yes	The instance name.
User	String	Yes	The username.
Password	String	Yes	The password.
Level	String	Yes	Instance types
Config	String	No	The custom my.cnf configuration of the instance, which is in the JSON format. The key must be the same as the value of the field in my.cnf, which is of the string type.

Response parameters

[Common response parameters](#)

Examples

Sample requests

```
curl 'xdb-master.xdb.env8c-inc.com:15678? Action=CreateInstance&InstanceName=xdb-instance-1&User=admin&password=xdb&Level=rds.mys2.small'
```

Sample responses

```
{
  "Result": "Task has created, you can use api(DescribeTaskProgress) to get task progress",
  "RequestID": "8BCB3B39-6140-459F-B283-F83C03ADC3CA"
}
```

5.3.1.10.3.4 DeleteInstance

Deletes an instance.

Description

Deletes an instance. This is an asynchronous task. You can view the task result by calling the DescribeTaskProgress API based on the RequestID in the responses.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: DeleteInstance
InstanceName	String	Yes	The instance name.

Response parameters

[Common response parameters](#)

Examples

Sample requests

```
curl '127.0.0.1:15678? Action=DeleteInstance&InstanceName=xdb-instance-1'
```

Sample responses

```
{
```



```
"Result": "Task has created, you can use api(DescribeTaskProgress) to get task progress
.",
"RequestID": "9C40CCB3-4FAB-4242-9B87-792E8154E5CD"
}
```

5.3.1.10.3.5 RestartInstance

Restarts an instance.

Description

Restarts an instance. This is an asynchronous task. You can view the task result by calling the DescribeTaskProgress API based on the RequestID in the responses.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: RestartInstance
InstanceName	String	Yes	The instance name.

Response parameters

[Common response parameters](#)

Examples

Sample requests

```
curl 'xdb-master.xdb.env8c-inc.com:15678? Action=RestartInstance&InstanceName=xdb-
instance-2'
```

Sample responses

```
{
  "Result": "Task has created, you can use api(DescribeTaskProgress) to get task progress
.",
  "RequestID": "47277A23-5FFE-4A46-B65F-E6F2569F44E5"
}
```

}

5.3.1.10.3.6 UpgradeInstance

Performs a minor upgrade of an instance.

Description

Performs a minor upgrade of an instance. This is an asynchronous task. You can view the task result by calling the DescribeTaskProgress API based on the RequestID in the responses .

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: UpgradeInstance
InstanceName	String	Yes	The instance name.

Response parameters

[Common response parameters](#)

Examples

Sample requests

```
curl 'xdb-master.xdb.env8c-inc.com:15678? Action=UpgradeInstance&InstanceName=xdb-instance-2'
```

Sample responses

```
{
  "Result": "Task has created, you can use api(DescribeTaskProgress) to get task progress",
  "RequestID": "95E8B098-B04A-4BCA-BEBE-DA1D11BBAD4A"
}
```

5.3.1.10.3.7 DescribeTaskProgress

Views the task progress.

Description

Views the task progress.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value : DescribeTaskProgress
RequestID	String	Yes	The request ID.

Response parameters

For more information about the common response parameters, see [Common response parameters](#).

Name	Type	Required	Description
Progress	String	Yes	The instance progress, including pending, doing, done, and failed.
Description	String	Yes	The description of the instance progress .

Examples

Sample requests

```
curl 'xdb-master.xdb.env8c-inc.com:15678? Action=DescribeTaskProgress&RequestID=47277A23-5FFE-4A46-B65F-E6F2569F44E5'
```

Sample responses

```
{
  "Result": {
    "Progress": "done",
    "Description": "Success"
  },
  "RequestID": "AC535130-F40E-4D45-BC05-0F45C8473346"
```

```
}
```

5.3.1.10.3.8 ChangeLeaderTo

Changes the leader role of an instance to another node.

Description

Changes the leader role of an instance to another node.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: ChangeLeaderTo
InstanceName	String	Yes	The instance name.
IP	String	Yes	The IP address of the machine where the new leader node is located.

Response parameters

[Common response parameters](#)

Examples

Sample requests

```
curl 'xdb-master.xdb.env8c-inc.com:15678? Action=ChangeLeaderTo&InstanceName=xdb-instance-1&IP=10.39.XX.XX'
```

Sample responses

```
{
  "Result": "Success",
  "RequestID": "37638DE5-14C1-4D2E-984F-FEA1F29C9F84"
```

```
}
```

5.3.1.10.3.9 ModifyInstanceLevel

Modifies the instance specifications.

Description

Modifies the instance specifications. This is an asynchronous task. You can view the task result by calling the DescribeTaskProgress API based on the RequestID in the responses.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: ModifyInstanceLevel
InstanceName	String	Yes	The instance name.
Level	String	Yes	The new instance specifications.

Response parameters

[Common response parameters](#)

Examples

Sample requests

```
curl 'xdb-master.xdb.env8c-inc.com:15678? Action=ModifyInstanceLevel&InstanceName=xdb-instance-1&Level=rds.mys2.mid'
```

Sample responses

```
{
  "Result": "Task has created, you can use api(DescribeTaskProgress) to get task progress",
  "RequestID": "21B91211-BB09-4665-835D-9471A6F07F24"
```

```
}
```

5.3.1.10.3.10 DescribeLeader

Views the primary node information of an instance.

Description

Views the primary node information of an instance.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: DescribeLeader
InstanceName	String	Yes	The instance name.

Response parameters

For more information about the common response parameters, see [Common response parameters](#).

Name	Type	Required	Description
LeaderIP	String	Yes	The IP address of the primary node.
Port	Integer	Yes	The instance port.
User	String	Yes	The username.
Password	String	Yes	The password.

Examples

Sample requests

```
curl 'xdb-master.xdb.env8c-inc.com:15678? Action=DescribeLeader&InstanceName=xdb-meta'
```

Sample responses

```
{
  "Result": {
    "LeaderIP": "10.27.XX.XX",
    "Password": "xdb",
```

```

    "Port": 3606,
    "User": "xdb"
  },
  "RequestID": "2F05EE81-DC47-478E-9CA9-9AE8CA809151"
}

```

5.3.1.10.3.11 RecreateNode

Recreates an instance node.

Description

Uses other available nodes to recreate an instance node by backup and recovery. This is an asynchronous task. You can view the task result by calling the DescribeTaskProgress API based on the RequestID in the responses.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: RecreateNode
InstanceName	String	Yes	The instance name.
IP	String	Yes	The IP address of the instance node to be recreated.

Response parameters

[Common response parameters](#)

Examples

Sample requests

```
curl 'xdb-master.xdb.env8c-inc.com:15678? Action=RecreateNode&InstanceName=xdb-instance-1&IP=10.39.XX.XX'
```

Sample responses

```

{
  "Result": "Task has created, you can use api(DescribeTaskProgress) to get task progress",
  "RequestID": "7F079E11-1DE9-4148-A9FA-683E4C58F9C2"
}

```

```
}
```

5.3.1.10.3.12 CreateDatabase

Creates a database and a user.

Description

Creates a database and a user.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: CreateDatabase
InstanceName	String	Yes	The instance name.
DBName	String	Yes	The database name.
User	String	Yes	The username.
Password	String	Yes	The password.

Response parameters

[Common response parameters](#)

Examples

Sample requests

```
curl 'xdb-master.xdb.env8c-inc.com:15678? Action=CreateDatabase&InstanceName=xdb-instance-1&DBName=xdb&User=admin&Password=xdb_password'
```

Sample responses

```
{
  "Result": "Success",
  "RequestID": "A2BEF74F-5C3A-4CEF-A2B8-C14C71E36569"
```



```
}
```

5.3.1.10.3.13 DeleteDatabase

Deletes a database.

Description

Deletes a database.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: DeleteDatabase
InstanceName	String	Yes	The instance name.
DBName	String	Yes	The name of the database to be deleted.

Response parameters

[Common response parameters](#)

Examples

Sample requests

```
curl 'xdb-master.xdb.env8c-inc.com:15678? Action=DeleteDatabase&InstanceName=xdb-instance-1&DBName=xdb'
```

Sample responses

```
{
  "Result": "Success",
  "RequestID": "23F75A0A-B1D6-4341-BD5B-1A5F3FD45848"
}
```

5.3.1.10.3.14 DeleteUser

Deletes a user.

Description

Deletes a user.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: DeleteUser
InstanceName	String	Yes	The instance name.
User	String	Yes	The username.
Host	String	No	The source address range. If not configured, the user account is deleted in all of the source addresses by default.

Response parameters

[Common response parameters](#)

Examples

Sample requests

```
curl 'xdb-master.xdb.env8c-inc.com:15678? Action=DeleteUser&InstanceName=xdb-instance-1&User=admin&Host=10.39.XX.XX'
```

Sample responses

```
{
  "Result": "Success",
  "RequestID": "6A82AFF6-2B4D-48EF-868D-BBA54667D846"
}
```

5.3.1.10.4 APIs on the deployment side

5.3.1.10.4.1 CheckHealth

Checks if an instance node is of the leader role and whether the status is readable and writeable.

Description

Checks if an instance node is of the leader role. An instance node is regarded as healthy only if it is of the leader role and is readable and writeable.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: CheckHealth
Port	Integer	Yes	The port of the instance node.

Response parameters

For more information about the common response parameters, see [Common response parameters](#).

Name	Type	Required	Description
health	Boolean	Yes	The health status.

Examples

Sample requests

```
curl '127.0.XX.XX:18765? Action=CheckHealth&Port=3606'
```

Sample responses

```
{
  "Result": {
    "health": true
  },
  "RequestID": "304B69CE-1566-4E87-B618-233F40238FFF"
}
```

```
{
  "Message": "{ \"health\": false }",
}
```

```
"Code": "NodeNotHealth",  
"RequestID": "E939DB9B-4337-4B1C-8680-F62BEDD645DC"  
}
```

5.3.1.10.4.2 CheckState

Checks whether the status of an instance node is normal.

Description

Checks whether the status of an instance node is normal. Generally, you have the following two situations:

- The node is of the leader role and is readable and writeable.
- The node is of the follower role and is readable.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: CheckState
Port	Integer	Yes	The port of the instance node.

Response parameters

For more information about the common response parameters, see [Common response parameters](#).

Name	Type	Required	Description
IP	String	Yes	The IP address of the instance node.
Port	Integer	Yes	The instance port.
Role	String	Yes	The role of the instance node.
Writable	String	Yes	Whether the instance node is writeable.
Readable	String	Yes	Whether the instance node is readable.

Name	Type	Required	Description
State	String	Yes	The status of the instance node. If the status is normal, the value is GOOD. Otherwise, the value is ERROR.

Examples

Sample requests

```
curl '127.0.XX.XX:18765? Action=CheckState&Port=3606'
```

Sample responses

```
{
  "Result": {
    "Readable": true,
    "State": "GOOD",
    "Role": "Follower",
    "Port": 3606,
    "IP": "10.39.XX.XX"
  },
  "RequestID": "45A59426-46D3-4709-8DD6-CD9F243336E0"
}
```

5.3.1.10.4.3 DescribeNodeStatus

Views the status of an instance node.

Description

Views the status of an instance node. A leader node is readable and writeable, while a follower node is readable.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: DescribeNodeStatus

Name	Type	Required	Description
Port	Integer	Yes	The port of the instance node. This parameter is required if the instance mode is single_machine.

Response parameters

For more information about the common response parameters, see [Common response parameters](#).

Name	Type	Required	Description
IP	String	Yes	The IP address of the instance node.
Port	Integer	Yes	The port of the instance node.
Role	String	Yes	The instance role.
Writeable	String	Yes	Whether the instance node is writeable.
Readable	String	Yes	Whether the instance node is readable.
ConnectionCount	Integer/String	Yes	The number of connections. If the retrieval fails, the value is unknown.
MaxConnectionCount	Integer/String	Yes	The maximum number of connections. If the retrieval fails, the value is unknown.
ConnectionPercent	Integer/String	Yes	The percentage of connections. If the retrieval fails, the value is unknown.
QPS	Integer/String	Yes	Queries per second (QPS). If the retrieval fails, the value is unknown.

Name	Type	Required	Description
CpuPercent	Integer/String	Yes	The CPU usage. If the retrieval fails, the value is unknown.
MemoryPercent	Integer/String	Yes	The memory usage. If the retrieval fails, the value is unknown.
DiskPercent	Integer/String	Yes	The disk usage. If the retrieval fails, the value is unknown.
State	String	Yes	The status of the instance node. If the status is normal, the value is GOOD. Otherwise, the value is ERROR.

Examples

Sample requests

```
curl '127.0.XX.XX:18765? Action=DescribeNodeStatus&Port=3606'
```

Sample responses

```
{
  "Result": {
    "CpuPercent": 2.74,
    "IP": "10.39.XX.XX",
    "Readable": true,
    "MemoryPercent": 56.13,
    "State": "GOOD",
    "Role": "Follower",
    "MaxConnectionCount": 500,
    "ActiveThreadCount": 34,
    "Writeable": false,
    "ConnectionCount": 37,
    "DiskPercent": 3.0,
    "ConnectionPercent": 7.4,
    "QPS": 15.95,
    "Port": 3606
  },
  "RequestID": "D18328B1-78A9-4F3E-BB2E-B27AB7683C19"
```

```
}
```

5.3.1.10.4 ListNode

Lists instance nodes.

Description

Lists the basic information of instance nodes.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: ListNode

Response parameters

For more information about the common response parameters, see [Common response parameters](#).

Name	Type	Required	Description
Nodes	String	Yes	The list of instance names.

Examples

Sample requests

```
curl '127.0.XX.XX:18765? Action=ListNode'
```

Sample responses

```
{
  "Result": {
    "Nodes": [
      "xdb-instance-1",
      "xdb-instance-2",
      "xdb-instance-3",
      "xdb-meta"
    ]
  },
  "RequestID": "3F7BB536-FA3F-4597-A3DF-E5830F5A3A21"
```



```
}
```

5.3.1.10.4.5 BackupNode

Backs up data of an instance node and transmits the data to a specified location (Use the nc command to transmit data to the port of a specified IP address).

Description

Backs up data of an instance node and transmits the data to a specified location.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: BackupNode
Port	Integer	Yes	The instance port.
TargetIP	String	Yes	The IP address of the target location.
TargetPort	Integer	Yes	The port of the target location.

Response parameters

[Common response parameters](#)

Examples

Sample requests

```
curl '127.0.XX.XX:18765? Action=BackupNode&Port=3606&TargetIP=10.39.XX.XX&TargetPort='
```

Sample responses

```
{
  "Result": "Success",
  "RequestID": "6A82AFF6-2B4D-48EF-868D-BBA54667D846"
```

```
}
```

5.3.1.11 Appendix

5.3.1.11.1 IP list

This report displays the IP addresses of physical machines and Docker applications.

IP List of Physical Machines

Item	Description
Project	The project name.
Cluster	The cluster name.
Machine Name	The hostname of the machine.
IP	The IP address of the machine.

IP List of Docker Applications

Item	Description
Project	The project name.
Cluster	The cluster name.
Service	The service name.
Server Role	The server role name.
Machine Name	The hostname of the machine.
Docker Host	The Docker hostname.
Docker IP	The Docker IP address.

5.3.1.11.2 Project component info report

This report displays the name and status for each type of project components, including services, server roles, and machines.

Item	Description
Project	The project name.
Cluster	The name of a cluster in the project.
Service	The name of a service in the cluster.
Server Role	The name of a server role in the service.
Server Role Status	The running status of the server role on the machine.

Item	Description
Server Role Action	The action that the server role performs on the machine. Data is available only when Apsara Infrastructure Management Framework asks the server role to perform certain actions, such as rolling and restart actions.
Machine Name	The hostname of the machine.
IP	The IP address of the machine.
Machine Status	The running status of the machine.
Machine Action	The action that Apsara Infrastructure Management Framework asks the machine to perform, such as the clone action.

5.3.1.11.3 Machine info report

This report displays the statuses of machines and server roles on the machines.

Machine Status

Displays all the machines currently managed by Apsara Infrastructure Management Framework and their corresponding statuses. In the **Global Filter** section at the top of the page, select the project, cluster, and machine from the **project**, **cluster**, and **machine** drop-down lists, and then click **Filter** on the right to filter the data.

Item	Description
Machine Name	The machine name.
IP	The IP address of the machine.
Machine Status	The machine status.
Machine Action	The action currently performed by the machine.
Machine Action Status	The action status.
Status Description	The description about the machine status.

Expected Server Role List

Select a row in the **Machine Status** section to display the corresponding information in this list.

Item	Description
Machine Name	The machine name.
Server Role	The name of the expected server role on the machine.

Abnormal Monitoring Status

Select a row in the **Machine Status** section to display the corresponding information in this list.

Item	Description
Machine Name	The machine name.
Monitored Item	The name of the monitored item.
Level	The level of the monitored item.
Description	The description of the monitored item contents.
Updated At	The updated time of the monitored item.

Server Role Version and Status on Machine

Select a row in the **Machine Status** section to display the corresponding information in this list.

Item	Description
Machine Name	The machine name.
Server Role	The server role name.
Server Role Status	The status of the server role.
Target Version	The expected version of the server role on the machine.
Current Version	The current version of the server role on the machine.
Status Description	The description about the status.
Error Message	The exception message of the server role.

Monitoring Status

Select a row in the **Machine Status** section to display the corresponding information in this list.

Item	Description
Machine Name	The machine name.
Server Role	The server role name.
Monitored Item	The name of the monitored item.
Level	The level of the monitored item.
Description	The description of the monitored item contents.

Item	Description
Updated At	The updated time of the monitored item.

5.3.1.11.4 Rolling info report

This report displays the running and completed rolling tasks and the task-related status.

Choose a rolling action

This list only displays the running rolling tasks. If no rolling task is running, no data is available in the list.

Item	Description
Cluster	The cluster name.
Git Version	The version of change that triggers the rolling task.
Description	The description about the change entered by a user when the user submits the change.
Start Time	The start time of the rolling task.
End Time	The end time of the rolling task.
Submitted By	The ID of the user who submits the change.
Rolling Task Status	The current status of the rolling task.
Submitted At	The time when the change is submitted.

Server Role in Job

Select a rolling task in the **Choose a rolling action** section to display the rolling status of server roles related to the selected task. If no rolling task is selected, the server role statuses of all historical rolling tasks are displayed.

Item	Description
Server Role	The server role name.
Server Role Status	The rolling status of the server role.
Error Message	The exception message of the rolling task.
Git Version	The version of change to which the rolling task belongs.
Start Time	The start time of the rolling task.

Item	Description
End Time	The end time of the rolling task.
Approve Rate	The proportion of machines that have the rolling task approved by the decider.
Failure Rate	The proportion of machines that have the rolling task failed.
Success Rate	The proportion of machines that have the rolling task succeeded.

Server Role Rolling Build Information

The source version and target version of each application under the server role in the rolling process.

Item	Description
App	The name of the application that requires rolling in the server role.
Server Role	The server role to which the application belongs.
From Build	The version before the upgrade.
To Build	The version after the upgrade.

Server Role Statuses on Machines

Select a server role in the **Server Role in Job** section to display the deployment status of this server role on the machine.

Item	Description
Machine Name	The name of the machine on which the server role is deployed.
Expected Version	The target version of the rolling.
Actual Version	The current version.
State	The status of the server role.
Action Name	The Apsara Infrastructure Management Framework action currently performed by the server role.
Action Status	The action status.

5.3.1.11.5 Machine RMA approval pending list

Some Apsara Infrastructure Management Framework actions (such as restart) on machines and server roles can be triggered by users, but this type of actions must be reviewed and approved. This report is used to process the actions that must be reviewed and approved.

Machine

Displays the basic information of pending approval machines.

Item	Description
Project	The project name.
Cluster	The cluster name.
Hostname	The hostname of the machine.
IP	The IP address of the machine.
State	The running status of the machine.
Action Name	The action on the machine.
Action Status	The status of the action on the machine.
Actions	The approval button.

Machine Serverrole

Displays the information of server roles on the pending approval machines.

Item	Description
Project	The project name.
Cluster	The cluster name.
Hostname	The hostname of the machine.
IP	The IP address of the machine.
Serverrole	The server role name.
State	The running status of the server role.
Action Name	The action on the server role.
Action Status	The status of the action on the server role.
Actions	The approval button.

Machine Component

Displays the hard disk information of pending approval machines.

Item	Description
Project	The project name.
Cluster	The cluster name.
Hostname	The hostname of the machine.
Component	The hard disk on the machine.
State	The running status of the hard disk.
Action Name	The action on the hard disk.
Action Status	The status of the action on the hard disk.
Actions	The approval button.

5.3.1.11.6 Registration vars of services

This report displays values of all service registration variables.

Item	Description
Service	The service name.
Service Registration	The service registration variable.
Cluster	The cluster name.
Update Time	The updated time.

5.3.1.11.7 Virtual machine mappings

Use the global filter to display the virtual machines of a specific cluster.

Displays the information of virtual machines in the cluster. Data is available only when virtual machines are deployed in the cluster.

Item	Description
Project	The project name.
Cluster	The cluster name.
VM	The hostname of the virtual machine.
Currently Deployed On	The hostname of the physical machine on which the virtual machine is currently deployed.
Target Deployed On	The hostname of the physical machine on which the virtual machine is expected to be deployed.

5.3.1.11.8 Service inspector report

Use the global filter to display the service inspection reports of a specific cluster.

Service Inspector: Data is available only for services with inspection configured.

Item	Description
Project	The project name.
Cluster	The cluster name.
Service	The service name.
Description	The contents of the inspection report.
Level	The level of the inspection report.

5.3.1.11.9 Resource application report

In the **Global Filter** section, select the project, cluster, and machine from the **project**, **cluster**, and **machine** drop-down lists and then click **Filter** on the right to display the corresponding resource application data.

Change Mappings

Item	Description
Project	The project name.
Cluster	The cluster name.
Version	The version where the change occurs.
Resource Process Status	The resource application status in the version.
Msg	The exception message.
Begintime	The start time of the change analysis.
Endtime	The end time of the change analysis.

Changed Resource List

Item	Description
Res	The resource ID.
Type	The resource type.
Name	The resource name.
Owner	The application to which the resource belongs.
Parameters	The resource parameters.

Item	Description
Ins	The resource instance name.
Instance ID	The resource instance ID.

Resource Status

Item	Description
Project	The project name.
Cluster	The cluster name.
Service	The service name.
Server Role	The server role name.
APP	The application of the server role.
Name	The resource name.
Type	The resource type.
Status	The resource application status.
Parameters	The resource parameters.
Result	The resource application result.
Res	The resource ID.
Reprocess Status	The status of the interaction with Business Foundation System during the VIP resource application.
Reprocess Msg	The error message of the interaction with Business Foundation System during the VIP resource application.
Reprocess Result	The result of the interaction with Business Foundation System during the VIP resource application.
Refer Version List	The version that uses the resource.
Error Msg	The exception message.

5.3.1.11.10 Statues of project components

This report displays the status of all server roles in an abnormal status on machines of the project, and the monitoring information (alert information reported by the server role to Apsara Infrastructure Management Framework monitor) of server roles and machines.

Error State Component Table

Only displays the information of server roles that are not in GOOD status and server roles to be upgraded.

Item	Description
Project	The project name.
Cluster	The cluster name.
Service	The service name.
Server Role	The server role name.
Machine Name	The machine name.
Need Upgrade	Whether the current version reaches the final status.
Server Role Status	The current status of the server role.
Machine Status	The current status of the machine.

Server Role Alert Information

Select a row in the **Error State Component Table** section to display the corresponding information in the list.

Item	Description
Cluster	The cluster name.
Service	The service name.
Server Role	The server role name.
Machine Name	The machine name.
Monitored Item	The monitored item name of the server role.
Level	The alert level.
Description	The description about the alert contents.
Updated At	The updated time of the alert information.

Machine Alert Information

Select a row in the **Error State Component Table** section to display the corresponding information in the list.

Item	Description
Cluster	The cluster name.
Machine Name	The machine name.
Monitored Item	The monitored item name of the server role.
Level	The alert level.

Item	Description
Description	The description about the alert contents.
Updated At	The updated time of the alert information.

Service Inspector Information

Select a row in the **Error State Component Table** section to display the corresponding information in the list.

Item	Description
Cluster	The cluster name.
Service	The service name.
Server Role	The server role name.
Monitored Item	The monitored item name of the server role.
Level	The alert level.
Description	The description about the alert contents.
Updated At	The updated time of the alert information.

5.3.1.11.11 Relationship of service dependency

This report displays the dependencies among server roles. Use the global filter to display the data of a specific cluster in the list.

Item	Description
Project	The project name.
Cluster	The cluster name.
Service	The service name.
Server Role	The server role name.
Dependent Service	The service on which the server role depends.
Dependent Server Role	The server role on which the server role depends.
Dependent Cluster	The cluster to which the dependent server role belongs.
Dependency in Final Status	Whether the dependent server role reaches the final status.

5.3.1.11.12 Check report of network topology

This report checks if network devices and machines have wirecheck alerts.

Check Report of Network Topology

Checks if network devices have wirecheck alerts.

Item	Description
Cluster	The cluster name.
Network Instance	The name of the network device.
Level	The alert level.
Description	The description about the alert information.

Check Report of Server Topology

Checks if servers (machines) have wirecheck alerts.

Item	Description
Cluster	The cluster name.
Machine Name	The server (machine) name.
Level	The alert level.
Description	The description about the alert information.

5.3.1.11.13 Clone report of machines

This report displays the clone progress and status of machines.

Clone Progress of Machines

Item	Description
Project	The project name.
Cluster	The cluster name.
Machine Name	The machine name.
Machine Status	The running status of the machine.
Clone Progress	The progress of the current clone process.

Clone Status of Machines

Item	Description
Project	The project name.

Item	Description
Cluster	The cluster name.
Machine Name	The machine name.
Machine Action	The action performed by the machine, such as the clone action.
Machine Action Status	The status of the action performed by the machine.
Machine Status	The running status of the machine.
Level	Whether the clone action performed by the machine is normal.
Clone Status	The current status of the clone action performed by the machine.

5.3.1.11.14 Auto healing/install approval pending report

The list structure is the same as the machine RMA approval pending list, whereas this view is used for the approval during the installation. For more information, see [Machine RMA approval pending list](#).

5.3.1.11.15 Machine power on or off statuses of clusters

After a cluster starts or shuts down machines, you can view the related information in this report.

Cluster Running Statuses

If a cluster is starting or shutting down machines, the corresponding data is available in this list. No data indicates that no cluster has machines shut down.

Item	Description
Project	The project name.
Cluster	The cluster name.
Action Name	The startup or shutdown action that is being performed by the cluster.
Action Status	The status of the action.

Server Role Power On or Off Statuses

Displays the power on or off statuses of server roles in the cluster selected in the **Cluster Running Statuses** section.

Select a row in the **Cluster Running Statuses** section to display the information of the corresponding cluster in the list.

Item	Description
Cluster	The cluster name.
Server Role	The server role name.
Action Name	The startup or shutdown action that is being performed by the server role.
Action Status	The status of the action.

Statuses on Machines

Displays the running status of the selected server role on machines.

Select a row in the **Server Role Power On or Off Statuses** section to display the information of the corresponding server role in the list.

Item	Description
Cluster	The cluster name.
Server Role	The server role name.
Machine Name	The machine name.
Server Role Status	The running status of the server role.
Server Role Action	The action currently performed by the server role.
Server Role Action Status	The status of the action.
Error Message	The exception message.

Machine Statuses

Displays the running statuses of machines in the selected cluster.

Select a row in the **Statuses on Machines** section to display the information of the corresponding machine in the list.

Item	Description
Cluster	The cluster name.
Machine Name	The machine name.
IP	The IP address of the machine.
Machine Status	The running status of the machine.
Machine Action	The action currently performed by the machine.

Item	Description
Machine Action Status	The action status of the machine.
Error Message	The exception message.

5.3.2 New version

5.3.2.1 What is Apsara Infrastructure Management Framework?

This topic describes what Apsara Infrastructure Management Framework is from the aspects of core functions and basic concepts.

5.3.2.1.1 Introduction

Apsara Infrastructure Management Framework is a distributed data center management system, which manages applications on clusters containing multiple machines and provides the basic functions such as deployment, upgrade, expansion, contraction, and configuration changes.

Overview

Apsara Infrastructure Management Framework also supports monitoring data and analyzing reports, which facilitates users to perform one-stop Operation & Maintenance (O&M) control. Based on the Apsara Infrastructure Management Framework services, automated O&M is implemented in the large-scale distributed environment, which greatly improves the operations efficiency and enhances the system availability.

Apsara Infrastructure Management Framework is mainly composed of TianjiMaster and TianjiClient. Apsara Infrastructure Management Framework installs TianjiClient as the agent on machines it manages. Then, TianjiMaster accepts and issues the upper-layer instructions to TianjiClient for execution. In the upper layer, Apsara Infrastructure Management Framework is divided into different components based on different functions, and then provides API server and portal for external use.

Core functions

- Network initialization in data centers
- Server installation and maintenance process management
- Deployment, expansion, and upgrade of cloud products
- Configuration management of cloud products
- Automatic application for cloud product resources

- Automatic repair of software and hardware faults
- Basic monitoring and business monitoring of software and hardware

5.3.2.1.2 Basic concepts

Before using Apsara Infrastructure Management Framework, you must know the following basic concepts for a better understanding.

project

A collection of clusters, which provides service capabilities for external entities.

cluster

A collection of physical machines, which logically provides services and is used to deploy project software.

- A cluster can only belong to one project.
- Multiple services can be deployed on a cluster.

service

A set of software, which provides relatively independent functions. A service is composed of one or more server roles and can be deployed on multiple clusters to form multiple sets of services and provide the corresponding service capabilities. For example, Apsara Distributed File System, Job Scheduler, and Apsara Name Service and Distributed Lock Synchronization System are all services.

service instance

A service that is deployed on a cluster.

server role

One or more indivisible deployment units into which a service can be divided based on functions. A server role is composed of one or more specific applications. If a service is deployed on a cluster, all the server roles of the service must be deployed to machines of this cluster. Multiple server roles, such as PanguMaster and TianjiClient, can be deployed on the same server.

server role instance

A server role that is deployed on a machine. A server role can be deployed on multiple machines.

application

Applications correspond to each process-level service component in a server role and each application works independently. The application is the minimum unit for deployment and upgrade in Apsara Infrastructure Management Framework, and can be deployed to each machine. Generally, an application is an executable software or Docker container.

If a server role is deployed on a machine, all applications in the server role must be deployed to this machine.

rolling

Each time when a user updates configurations, Apsara Infrastructure Management Framework upgrades services and modifies the cluster configurations based on the updated configurations. This process is called rolling.

service configuration template

Some configurations are the same when services are deployed on clusters. A service configuration template can be created to quickly write the same configurations to different clusters. The service configuration template is basically used for large-scale deployment and upgrade.

associated service template

A template.conf file that exists in the configurations. This file declares the service configuration template and its version, of which the configuration is used by the service instance.

desired state

If a cluster is in this state, all hardware and software on each of its machines are normal and all software are in the target version.

dependency

The dependency between server roles in a service defines that server roles with dependencies run tasks or are upgraded based on the dependency order. For example, if A depends on B, B is upgraded first. A starts to be downloaded after B is downloaded successfully, and upgraded after B is successfully upgraded. (By default, the dependency does not take effect for configuration upgrade.)

upgrade

A way of aligning the current state with the desired state of a service. After a user submits the version change, Apsara Infrastructure Management Framework upgrades the service

version to the target version. With the server role as the processing unit, upgrade aims to update the versions of all machines to the target version.

At the beginning, the desired state and current state of the cluster are the same. When a user submits the change, the desired state is changed, whereas the current state is not. A rolling task is generated and has the desired state as the target version. During the upgrade, the current state is continuously approximating to the desired state. Finally, the desired state and the current state are the same when the upgrade is finished.

5.3.2.2 Log on to Apsara Infrastructure Management Framework


This topic describes how to log on to Apsara Infrastructure Management Framework.

Prerequisites

- ASO access address in the format of `http://region-id.aso.intranet-domain-id.com`.
- Google Chrome browser (recommended).

Procedure

1. Open the browser.
2. Enter the ASO access address `http://region-id.aso.intranet-domain-id.com` in the address bar and then press Enter.

The screenshot shows a dark-themed login interface. At the top, the text "Log On" is displayed in a light blue font. Below this, there are two input fields. The first field is preceded by a user icon and contains the placeholder text "Enter a user name". The second field is preceded by a lock icon and contains the placeholder text "Enter the password". At the bottom of the form, there is a prominent blue button with the text "Log On" in white.

Note:

You can select the language from the drop-down list in the upper-right corner to change the language of ASO.

3. Enter the correct username and password.



Note:

Obtain the username and password used to log on to ASO from the deployment personnel or the administrator.

- The system has three default users:
 - Security officer: manages other users or roles.
 - Auditor officer: views audit logs.
 - System administrator: used for other functions except those of the security officer and auditor officer.
- You must modify the password of your username as instructed when you log on to ASO for the first time. To improve security, the password must be 10-20 characters long and can contain English uppercase/lowercase letters (A-Z or a-z), numbers (0-9), and special characters, such as exclamation points (!), at signs (@), number signs (#), dollar signs (\$), and percent signs (%), which meets the minimum complexity requirements.

4. Click **Log On to log on to ASO.**

5. In the left-side navigation pane, select **Products.**


6. In the Product List, select **Apsara Infrastructure Management Framework.**

5.3.2.3 Homepage introduction

After you log on to Apsara Infrastructure Management Framework, the homepage appears. This topic allows you to get a general understanding of the basic operations and functions of Apsara Infrastructure Management Framework.

[Log on to Apsara Infrastructure Management Framework](#). The homepage appears, as shown in the following figure.


Figure 5-2: Homepage of Apsara Infrastructure Management Framework



For more information about the descriptions of functional areas on the homepage, see the following table.

Table 5-7: Descriptions of functional areas

Area		Description
1	Left-side navigation pane	<ul style="list-style-type: none"> • Operations: the quick entrance of Operation & Maintenance (O&M) operations, which allows operations engineers to quickly find the corresponding operations and operation objects. This menu consists of the following sections: <ul style="list-style-type: none"> - Project Operations: manages projects with the project permissions. - Cluster Operations: performs O&M operations on and manages clusters with the project permissions, such as viewing the cluster status. - Service Operations: manages services with the service permissions, such as viewing the service list information. - Machine Operations: maintains and manages all the machines in Apsara Infrastructure Management Framework, such as viewing the machine status. • Tasks: A rolling task is generated after you modify the configurations in the system. In this menu, you can view running tasks, history tasks, and the deployment summary of clusters, services, and server roles in all projects. • Reports: displays the monitoring data in tables and provides the function of searching for different reports. • Monitoring: effectively monitors metrics in the process of system operation and sends alert notifications for abnormal conditions. This menu includes the functions of displaying alert status, modifying alert rules, and searching for the alert history. • Tools: provides the machine tools and the IDC shutdown function.

Area		Description
2	Function buttons in the upper-right corner	<ul style="list-style-type: none"> Search box: Supports global search. Enter a keyword in the search box to search for clusters, services, and machines. Move the pointer over the time and then you can view: <ul style="list-style-type: none"> TJDB Sync Time: the generated time of the data that is displayed on the current page. Desired State Calc Time: the calculation time of the desired-state data that is displayed on the current page. <p>After data is generated, the system processes the data at maximum speed. As an asynchronous system, Apsara Infrastructure Management Framework has some latency . The time helps explain why the current data results are generated and determine whether the current system has a problem.</p> <ul style="list-style-type: none"> : In the English environment, click this drop-down list to switch to another language. Click the avatar of the logon user and then select Exit to log out of Apsara Infrastructure Management Framework.
3	Status section of global resources	<p>Displays the overview of global resources.</p> <ul style="list-style-type: none"> Clusters: displays the total number of clusters, the percentage of clusters that reach the desired state, and the number of abnormal clusters. Instances: displays the total number of instances, the percentage of instances that reach the desired state, and the number of abnormal instances. Machines: displays the total number of machines, the percentage of machines with the Normal state, and the number of abnormal machines. <p>Move the pointer over the section and then click Show Detail to go to the Cluster Operations page, Service Operations page, or Machine Operations page.</p>
4	Task status section	<p>Displays the information of tasks submitted in the last week. Click the number at the right of a task status to go to the My Tasks page and then view tasks of the corresponding status.</p> <p>The top 5 latest tasks are displayed at the bottom of this section and you can click Details to view the task details.</p>


Area		Description
5	Quick actions	Displays links of common quick actions, which allows you to perform operations quickly.
6	Expand/collapse button	If you are not required to use the left-side navigation pane when performing O&M operations, click this button to collapse the left-side navigation pane and increase the space of the content area.

5.3.2.4 Project operations

The Project Operations module allows you to search for and view details of a project.

Procedure

1. [Log on to Apsara Infrastructure Management Framework.](#)
2. In the left-side navigation pane, choose **Operations > Project Operations**.



3. On this page, you can:

- Search for a project

Click the drop-down list in the upper-right corner of the **Project Status** section. Enter a project name in the search box, and then select the name to search for the project. You can view the numbers of alerts and running tasks for the project and whether the project reaches the desired state.

- View the details of a project
 - Find the project whose details you are about to view. Click the number at the right of **Alerting**. In the displayed Alert Information dialog box, view the specific

monitoring metrics, monitoring types, and alert sources. Click the value in the Alert Source column to view the service details.

- Find the project whose details you are about to view. Click the number at the right of **In Progress**. In the displayed Tasks dialog box, view the details of Upgrade Service and Machine Change.

5.3.2.5 Cluster operations

This topic describes the actions about cluster operations.

5.3.2.5.1 View the cluster list

The cluster list allows you to view all of the clusters and the corresponding information.




Procedure

1. [Log on to Apsara Infrastructure Management Framework](#).
2. To view the cluster list, you can:
 - On the **Homepage**, move the pointer over the **Clusters** section and then click Show Detail in the upper-right corner.
 - In the left-side navigation pane, choose **Operations > Cluster Operations**.

Clusters	Region	Status	Machine Status	Server Role Status	Task Status	Actions
acs	cn-*	Desired State	7 in Total Normal	14 in Total Normal	Successful	Operations
yundun-advance	cn-*	Not Desired State	3 in Total Normal	8 in Total Abnormal: 1	Failed	Operations
dauthProduct	cn-*	Desired State	2 in Total Normal	7 in Total Normal	Successful	Operations

On this page, you can view the following information.

Item	Description
Clusters	The cluster name. Click the cluster name to view the cluster details.
Region	The name of the region where the cluster is located.


Item	Description																
Status	<p>Indicates whether the cluster reaches the desired state. Use  to filter the clusters.</p> <ul style="list-style-type: none"> Desired State: All the clusters of a project reach the desired state. Not Desired State: After a project reaches the desired state for the first time, a server role does not reach the desired state because of undefined reasons. 																
Machine Status	The number of machines and the corresponding status in the cluster. Click the status to go to the Machines tab of the Cluster Details page.																
Server Role Status	<p>The number of server roles and the corresponding status in the cluster. Click the status to go to the Services tab of the Cluster Details page. Click Abnormal in the Server Role Status column to view all the abnormal server roles in the cluster in the displayed dialog box. Click View Details in the upper-right corner of the dialog box to go to the Services tab of the Cluster Details page.</p>  <p>The screenshot shows a dialog box titled 'Abnormal Server Roles' with a 'View Details' link in the top right. It contains a table of server roles:</p> <table border="1"> <thead> <tr> <th>Server Role</th> <th>Status</th> </tr> </thead> <tbody> <tr> <td>tianji.TianjiClient#</td> <td>Machine Error</td> </tr> <tr> <td>tianji-sshtunnel-client.SSH1</td> <td>Machine Error</td> </tr> <tr> <td>nuwa.NuwaConfig#</td> <td>Machine Error</td> </tr> <tr> <td>nuwa.NuwaProxy#</td> <td>The version is inconsistent.</td> </tr> <tr> <td>EcsTdc.Tdc#</td> <td>Machine Error</td> </tr> <tr> <td>EcsNbd.Nbd#</td> <td>Machine Error</td> </tr> <tr> <td>ecs-NcManager NcDownM</td> <td>Machine Error</td> </tr> </tbody> </table> <p>At the bottom right of the dialog box, it says 'Top 20'.</p>	Server Role	Status	tianji.TianjiClient#	Machine Error	tianji-sshtunnel-client.SSH1	Machine Error	nuwa.NuwaConfig#	Machine Error	nuwa.NuwaProxy#	The version is inconsistent.	EcsTdc.Tdc#	Machine Error	EcsNbd.Nbd#	Machine Error	ecs-NcManager NcDownM	Machine Error
Server Role	Status																
tianji.TianjiClient#	Machine Error																
tianji-sshtunnel-client.SSH1	Machine Error																
nuwa.NuwaConfig#	Machine Error																
nuwa.NuwaProxy#	The version is inconsistent.																
EcsTdc.Tdc#	Machine Error																
EcsNbd.Nbd#	Machine Error																
ecs-NcManager NcDownM	Machine Error																
Task Status	<p>The status of the task submitted to the cluster. Use  to filter the clusters. Click the status to view the task details.</p>																

5.3.2.5.2 View the cluster details

You can view the cluster statistics by viewing the cluster details.

Procedure

1. Log on to Apsara Infrastructure Management Framework.
2. In the left-side navigation pane, choose **Operations > Cluster Operations**.
3. Select a project from the Project drop-down list or enter the cluster name in the Clusters field to search for the corresponding cluster.
4. Find the cluster whose configurations you are about to view. Click the cluster name or **Operations** in the **Actions** column at the right of the cluster to go to the **Cluster Details** page.



Area	Item	Description
1	Status	<ul style="list-style-type: none"> • Desired State: All the clusters of this project reach the desired state. • Not Desired State: After the project reaches the desired state for the first time, a server role does not reach the desired state because of undefined reasons.
	Project	The project to which the cluster belongs.
	Region	The region to which the cluster belongs.
	Included Server Roles	The number of server roles included in the cluster.
	Included Machines	The number of machines included in the cluster.

Area	Item	Description
	Task Status	<p>The status of the current task. Click View to view the task details.</p> <ul style="list-style-type: none"> • Successful: indicates the task is successful. • Preparing: indicates data is being synchronized and the task is not started yet. • In Progress: indicates the cluster has a changing task. • Paused: indicates the task is paused • Failed: indicates the task failed. • Terminated: indicates the task is manually terminated.
	Clone Mode	<ul style="list-style-type: none"> • Mock Clone: The system is not cloned when a machine is added to the cluster. • Real Clone: The system is cloned when a machine is added to the cluster.
	System Configuration	The name of the system service template used by the cluster.
	Git Version	The change version to which the cluster belongs.
	Security Authentication	The access control among processes. Generally, the non-production environment uses the default configurations and does not perform the verification. In other cases, customize the configurations based on actual requirements to enable or disable the verification.

Area	Item	Description
	Type	<ul style="list-style-type: none"> • Ordinary Cluster: an operations unit facing to machine groups, where multiple services can be deployed. • Virtual Cluster: an operations unit facing to services, which can centrally manage software versions of machines of multiple physical clusters. • RDS: a type of cluster that renders special cgroup configurations according to a certain rule. • NETFRAME: a type of cluster that renders special configurations for the special scenario of Server Load Balancer (SLB). • T4: a type of cluster that renders special configurations for the mixed deployment of e-commerce. <p>Currently, Alibaba Cloud Apsara Stack only has ordinary clusters.</p>
2	Services	<p>View the statuses of all the services in this cluster. You can also upgrade or unpublish a service.</p> <ul style="list-style-type: none"> • Normal: The service works properly. • Not Deployed: No machine is deployed on the service. • Changing: Some server roles in the service are changing. • Operating: No server role is changing, but the machine where server roles are installed is performing the Operation and Maintenance (O&M) operations. • Abnormal: No server role is changing or the machine where server roles are installed is not performing the O&M operations, but the server role status is not GOOD or the version that the service runs on the machine and the version configured in the configurations are different.
	Machines	<p>View the running statuses and monitoring statuses of all the machines in this cluster. You can also view the details of server roles to which the machine belongs.</p>

Area	Item	Description
	Cluster Configuration	The configuration file used in the cluster.
	Operation Log	View the version differences.
	Cluster Resource	Filter the resource whose details you are about to view according to certain conditions.
	Service Inspection	View the inspection information of each service in the cluster.

5.3.2.5.3 View operation logs

By viewing operation logs, you can obtain the differences between Git versions.

Procedure

1. [Log on to Apsara Infrastructure Management Framework.](#)
2. To view the operation logs of a cluster, you can:
 - Enter a cluster name in the search box in the upper-right corner of the page. Click **Operations** at the right of the cluster to go to the Cluster Details page. Click the **Operation Log** tab.
 - In the left-side navigation pane, choose **Operations > Cluster Operations**. On the **Cluster Operations** page, click **Operations** in the **Actions** column at the right of a cluster to go to the Cluster Details page. Click the **Operation Log** tab.

Services	Machines	Cluster Configuration	Operation Log	Cluster Resource	Service Inspection
Submission Time	12/04/19	12/11/19	Submitter	Please input	Services All
Refresh					
Description	Operation Type	Status	Git Version	Submitter	Actions
commit by tianji importer		Successful	4f19d86c3350bc71878481562e4938001e887fac	alljuntest Dec 05, 2019, 23:39:18	View Version Differences Details
total 1 items 1 10/Page Go to 1 Page					

3. On the **Operation Log** tab, view the version differences.
 - a) Click **View Version Differences** in the **Actions** column at the right of a log.
 - b) On the **Version Differences** page, select a basic version from the **Versus** drop-down list. Then, the contents of the different file are automatically displayed.
 - c) Select each different file from the **Different File** drop-down list to view the detailed differences.

5.3.2.6 Service operations

5.3.2.6.1 View the service list

The service list allows you to view all of the services and the corresponding information.

Procedure

1. [Log on to Apsara Infrastructure Management Framework.](#)
2. To view the service list, you can:
 - On the **Homepage**, move the pointer over the **Instances** section and then click Show Detail in the upper-right corner.
 - In the left-side navigation pane, choose **Operations > Service Operations**.

Services	Description	Clusters	Included Service Templates	Actions
Ali-tanji-machine-decider		1 in Total Desired State: 1	0	Operations
EcsBssTools		3 in Total Desired State: 3	1	Operations
EcsNod		5 in Total Desired State: 4 Not Desired State: 1	1	Operations
EcsRiver		3 in Total Desired State: 3	2	Operations
EcsRiverOSInit		1 in Total Desired State: 1	1	Operations
EcsRiverMaster		1 in Total Desired State: 1	1	Operations
EcsStorageMonitor		5 in Total Desired State: 4 Not Desired State: 1	1	Operations
EcsTdc		5 in Total Desired State: 4 Not Desired State: 1	3	Operations
RanderTestService1		0 in Total	0	Operations Delete
RanderTestService2		0 in Total	0	Operations Delete

total 412 items | 1 2 3 4 ... 42 | 10/10 Page | Go to 1 Page

On this page, you can view the following information.

Item	Description
Services	The service name. Click the service name to view the service details.
Clusters	The number of clusters where the service is located and the corresponding cluster status.
Included Service Templates	The number of service templates this service includes.
Actions	Click Operations to go to the Service Details page.

3. Enter a service name in the search box and then the service that meets the condition is displayed in the list.

5.3.2.6.2 View the server role details

You can view the server role statistics by viewing the server role details.

Procedure

1. [Log on to Apsara Infrastructure Management Framework.](#)

2. In the left-side navigation pane, choose **Operations** > **Service Operations**.
3. Enter a service name in the search box and then the service that meets the condition is displayed in the list.
4. Click the service name or click **Operations** in the **Actions** column.

Services EcsNbd

Included Clusters: 5 Included Server Roles: 2 Included Service Templates: 1

Clusters Service Template

Project: All Clusters: Enter a cluster name Template: Please select

Template: Please select Tag: Please select Batch Add Tags

<input type="checkbox"/>	Clusters	Region	Status	Server Role Status	Machine Status	Task Status	Template	Actions
<input type="checkbox"/>	ecs-289b	cn-...	Not Desired State	2 in Total Abnormal: 2	1 in Total Abnormal Server Roles: 0 Abnormal Machines: 1	Successful	TMPL_ECS_V707_TIANJIL_V4	Operations Task Details
<input type="checkbox"/>	ecs-ac1c	cn-...	Desired State	2 in Total Normal	5 in Total Normal	Successful	TMPL_ECS_V707_TIANJIL_V4	Operations Task Details
<input type="checkbox"/>	ecs-60db	cn-...	Desired State	2 in Total Normal	6 in Total Normal	Successful	TMPL_ECS_V707_TIANJIL_V4	Operations Task Details
<input type="checkbox"/>	ecs-288c	cn-...	Desired State	2 in Total Normal	4 in Total Normal	Successful	TMPL_ECS_V707_TIANJIL_V4	Operations Task Details
<input type="checkbox"/>	ecs-25a7	cn-...	Desired State	2 in Total Normal	13 in Total Normal	Successful	TMPL_ECS_V707_TIANJIL_V4	Operations Task Details

total 5 items 1/10 Page Go to 1 Page

5. On the **Clusters** tab, click the status in the Server Role Status column to view the server roles included in a cluster.

Service Details ECS-I011-A-ac1c / EcsNbd

Server Role: Enter a server role Refresh

EcsNbd.Guestf5d# EcsNbd.Nbd#

Diagnostic Mode: ☐

All: 5 ☐ Normal (5) Reset

Machines: Enter one or more hostnames/IP addresses Batch Terminal

<input type="checkbox"/>	Machines	Server Role Status	Metric	Actions
<input type="checkbox"/>	antest73	Normal Details	View	Terminal Restart Server Role
<input type="checkbox"/>	antest73	Normal Details	View	Terminal Restart Server Role
<input type="checkbox"/>	antest73	Normal Details	View	Terminal Restart Server Role
<input type="checkbox"/>	antest73	Normal Details	View	Terminal Restart Server Role
<input type="checkbox"/>	antest73	Normal Details	View	Terminal Restart Server Role

total 5 items 1/10 Page Go to 1 Page

6. Enter a keyword in the search box to search for a server role. Then, the details of the corresponding server role are displayed in the list.

Item	Description
Machines	The machine to which the server role belongs. Click the machine name to view the machine details.
Server Role Status	The status of the server role. Click Details to view the basic information, application version information, application process information, and resources of the server role.

Item	Description
Metric	Click View to view the statuses of server role metrics and machine metrics.
Actions	<ul style="list-style-type: none"> Click Terminal to log on to the machine and perform operations. Click Restart Server Role to restart the server role.

5.3.2.7 Machine operations

You can view the machine statistics by viewing the machine list.

Procedure

1. Log on to Apsara Infrastructure Management Framework.
2. To view the machine list, you can:
 - On the **Homepage**, move the pointer over the **Machines** section and then click Show Detail in the upper-right corner.
 - In the left-side navigation pane, choose **Operations > Machine Operations**.

Operations / Machine Operations

Machines

Project

All

 Clusters

Enter a cluster name


 Machines


Enter one or more hostnames/IP addresses

Batch Terminal

<input type="checkbox"/>	Hostname	Clusters	Project	Region	Status ▾	Machine Metrics	Actions
<input type="checkbox"/>	<div>amtest73</div>	<div>2898</div>	tianji	cn- <div></div>	<div>Normal</div> <div>Details</div>	<div>View</div>	<div>Operations Terminal Machine Management ▾</div>
<input type="checkbox"/>	<div>amtest73</div>	<div>2895</div>	yundun-advance	cn- <div></div>	<div>Normal</div> <div>Details</div>	<div>View</div>	<div>Operations Terminal Machine Management ▾</div>
<input type="checkbox"/>	<div>amtest73</div>	<div>2895</div>	slb	cn- <div></div>	<div>Normal</div> <div>Details</div>	<div>View</div>	<div>Operations Terminal Machine Management ▾</div>
<input type="checkbox"/>	<div>amtest73</div>	<div>2898</div>	tianji	cn- <div></div>	<div>Normal</div> <div>Details</div>	<div>View</div>	<div>Operations Terminal Machine Management ▾</div>
<input type="checkbox"/>	<div>amtest73</div>	<div>289d</div>	astc	cn- <div></div>	<div>Normal</div> <div>Details</div>	<div>View</div>	<div>Operations Terminal Machine Management ▾</div>
<input type="checkbox"/>	<div>amtest73</div>	<div>289d</div>	astc	cn- <div></div>	<div>Normal</div> <div>Details</div>	<div>View</div>	<div>Operations Terminal Machine Management ▾</div>
<input type="checkbox"/>	<div>amtest73</div>	<div>354e</div>	ads	cn- <div></div>	<div>Normal</div> <div>Details</div>	<div>View</div>	<div>Operations Terminal Machine Management ▾</div>
<input type="checkbox"/>	<div>amtest73</div>	<div>354e</div>	ads	cn- <div></div>	<div>Normal</div> <div>Details</div>	<div>View</div>	<div>Operations Terminal Machine Management ▾</div>
<input type="checkbox"/>	<div>amtest73</div>	<div>ec1c</div>	ecs	cn- <div></div>	<div>Normal</div> <div>Details</div>	<div>View</div>	<div>Operations Terminal Machine Management ▾</div>

3. Select a project or enter the cluster name or machine name to search for the corresponding machine.

Item	Description
Hostname	Click the hostname to go to the Machine Details page.
Status	<p>The current status of the machine. Use  to filter the machines.</p> <p>Click Details and then the Status Details of Machine dialog box appears.</p>

Item	Description
Machine Metrics	<p>Click View and then the Metrics dialog box appears.</p>  <p>The Server Role Metric tab and Machine Metrics tab display the corresponding metrics, and you can view the specific alert status and updated time.</p> <p>Enter a keyword in the search box in the upper-right corner to search for a server role or metric. You can also select the status to filter metrics.</p>
Actions	<ul style="list-style-type: none"> Click Operations to go to the Machine Details page. Click Terminal to log on to the machine and perform operations. You can select multiple machines and then click Batch Terminal in the upper-right corner to log on to multiple machines at a time. Click Machine Management to perform an out-of-band restart operation on the machine.

5.3.2.8 Monitoring center

You can view the alert status, alert rules, and alert history in the monitoring center.


5.3.2.8.1 View the monitoring instance status

You can view the status of a monitoring instance after it is deployed.

Procedure

1. Log on to [Apsara Infrastructure Management Framework](#).
2. In the left-side navigation pane, choose **Operations > Service Operations**.
3. Enter a service name in the search box to search for the corresponding service.
4. Click **Operations** in the **Actions** column at the right of the service.
5. On the **Clusters** tab, configure the conditions and then search for the cluster. Click **Operations** in the **Actions** column.

- On the **Cluster Details** page, select the server role you are about to view and then click **View** in the **Metric** column. Then, view the statuses of server role metrics and machine metrics.



5.3.2.8.2 View the alert status

The Alert Status page allows you to view the alerts generated in different services and the corresponding alert details.

Procedure

- Log on to [Apsara Infrastructure Management Framework](#).
- In the left-side navigation pane, choose **Monitoring**. On the Monitoring page, click **Go** to open the target page.
- In the top navigation bar, choose **Monitoring > Alert Status**.

Alert Status							
Service	All	Cluster	All	Enter an alert name.	Time Range	12/10/19, 20:10:00 ~ 12/11/19, 20:10:00	Search
Service	Cluster	Instance	Alert Status	Alert Level	Alert Name	Alert Time	Actions
tianji	slbCluster-A...	cluster=slbCluster-A-20191030-2885,host=a...	Alerting	P1	memo_cluster_host	11/23/19, 13:03:00 Lasted for 18 Days 7 Hours 7 Minutes 35 Seco nds	Show
tianji	slbCluster-A...	cluster=slbCluster-A-20191030-2885,host=a...	Alerting	P1	memo_cluster_host	11/23/19, 13:03:00 Lasted for 18 Days 7 Hours 7 Minutes 35 Seco nds	Show
tianji	mongodb-A...	cluster=mongodb-A-20191030-2885,host=a5...	Alerting	P1	memo_cluster_host	11/23/19, 13:04:00 Lasted for 18 Days 7 Hours 8 Minutes 35 Seco nds	Show
tianji	mongodb-A...	cluster=mongodb-A-20191030-2885,host=a5...	Alerting	P1	memo_cluster_host	11/23/19, 13:04:00 Lasted for 18 Days 7 Hours 8 Minutes 35 Seco nds	Show

- You can configure the service name, cluster name, alert name, or the time range when the alert is triggered to search for alerts.
- On the **Alert Status** page, view the alert details. For more information about the alert status descriptions, see the following table.

Item	Description
Service	The service name.

Item	Description
Cluster	The name of the cluster where the service is located.
Instance	The name of the service instance being monitored. Click the instance to view the alert history of this instance.
Alert Status	Alerts have two statuses: Restored and Alerting .
Alert Level	Alerts have the following four levels, from high to low, according to the effect on services. <ul style="list-style-type: none"> • P1 • P2 • P3 • P4
Alert Name	The name of the generated alert. Click the alert name to view the alert rule details.
Alert Time	The time when the alert is triggered and how long the alert has lasted.
Actions	Click Show to show the data before and after the alert time.

5.3.2.8.3 View alert rules

The Alert Rules page allows you to view the configured alert rules.

Procedure

1. Log on to Apsara Infrastructure Management Framework.
2. In the left-side navigation pane, choose **Monitoring**. On the Monitoring page, click **Go** to open the target page.
3. In the top navigation bar, choose **Monitoring > Alert Rules**.

Alert Rules						
Service	All	Cluster	All	Enter an alert name.	Search	
Service	Cluster	Alert Name	Alert Conditions	Periods	Alert Contact	Status
yundun-semawaf		semawaf_check_disk	\$Use>90	60		Running
yundun-semawaf		semawaf_check_disk	\$Use>90	60		Running
yundun-semawaf		app_vip_port_check_serverrole	\$state!=0,\$state!=0	60		Running
yundun-semawaf		alert_ping_yundun-soc	\$rta_avg>500(\$loss_max>80,\$rta_avg>400)(\$loss_max>80	60		Running
yundun-console-service		check_audit_log_openapi	\$totalcount>9	300		Running
yundun-console-service		check_sas_openapi	\$totalcount>9	300		Running
yundun-console-service		check_aesgis_openapi	\$totalcount>9	300		Running
yundun-console-service		check_secureservice_openapi	\$totalcount>9	300		Running
yundun-console-service		console-service_check_disk	long(\$size)>20971520	60		Running
yundun-console-service		check_aesgis_openapi	\$totalcount>9	300		Running

4. You can configure the service name, cluster name, or alert name to search for alert rules.
5. On the **Alert Rules** page, view the detailed alert rules. For more information about the alert rule descriptions, see the following table.

Item	Description
Service	The service name.
Cluster	The name of the cluster where the service is located.
Alert Name	The name of the generated alert.
Alert Conditions	The conditions met when the alert is triggered.
Periods	The frequency (in seconds) with which an alert rule is run.
Alert Contact	The groups and members that are notified when an alert is triggered.
Status	The current status of the alert rule. <ul style="list-style-type: none"> • Running: Click to stop the alert rule. • Stopped: Click to run the alert rule.

5.3.2.8.4 View the alert history

The Alert History page allows you to view all the history alerts generated in different services and the corresponding alert details.

Procedure

1. Log on to [Apsara Infrastructure Management Framework](#).
2. In the left-side navigation pane, choose Monitoring. On the **Monitoring** page, click **Go** to open the target page.
3. In the top navigation bar, choose **Monitoring > Alert History**.

Alert History								
<div> <div>Service</div> <div>All</div> <div>Cluster</div> <div>All</div> </div> <div> <div>1 Hour</div> <div>12 Hours</div> <div>1 Day</div> <div>1 Week</div> <div>1 Month</div> <div>3 Months</div> <div>Custom</div> <div>12/10/19, 20:16:00 ~ 12/11/19, 20:16:00</div> <div>Search</div> </div>								
Service	Cluster	Alert Instance	Status	Alert Level	Alert Name	Alert Time	Alert Contact	Actions
drds-console		service=drds-console.servicerole=drds-consol...	Restored	Restored	tianji_drds_prectrl_check_url	12/10/19, 20:38:13		Show
EcsTdc	288c	cluster=288c.servicerole=EcsTdc...	Alerting	P4	ecs_server_compute-cpu_usa...	12/10/19, 20:39:49		Show
EcsTdc	288c	cluster=288c.servicerole=EcsTdc...	Restored	Restored	ecs_server_compute-cpu_usa...	12/10/19, 20:41:49		Show
aso-systemMgr		service=aso-systemMgr.servicerole=aso-syste...	Alerting	P1	tianji_aso_auth_check_url	12/10/19, 21:45:25		Show
ecs-houyi	ECS-HOUYIRE...	cluster=28a2.servicerole=...	Alerting	P4	ecs-houyi_ecs_regionmaster-unknow_error	12/10/19, 21:57:39		Show
ecs-houyi	ECS-HOUYIRE...	cluster=28a2.servicerole=...	Restored	Restored	ecs-houyi_ecs_regionmaster-unknow_error	12/10/19, 22:06:39		Show

4. You can configure the service name, cluster name, time range, or period to search for alerts.


5. On the **Alert History** page, view the history alerts. For more information about the history alert descriptions, see the following table.

Item	Description
Service	The name of the service to which the alert belongs.
Cluster	The name of the cluster where the service is located.
Alert Instance	The name of the resource where the alert is triggered.
Status	Alerts have two statuses: Restored and Alerting .
Alert Level	Alerts have the following four levels, from high to low, according to the effect on services. <ul style="list-style-type: none"> • P1 • P2 • P3 • P4
Alert Name	The name of the generated alert. Click the alert name to view the alert rule details.
Alert Time	The time when the alert is triggered.
Alert Contact	The groups and members that are notified when an alert is triggered.
Actions	Click Show to show the data before and after the alert time.

5.3.2.9 View tasks

The task list allows you to view the submitted tasks and the corresponding status.

Procedure

1. [Log on to Apsara Infrastructure Management Framework](#)
2. To view the task list, you can:
 - In the left-side navigation pane, choose **Tasks > My Tasks**.
 - In the left-side navigation pane, choose **Tasks > Related Tasks**.
3. You can use  to filter tasks in the **Status** column.
4. Find the task whose details you are about to view and then click the task name or click **Details** in the **Actions** column.

5. On the **Task Details** page, view the status and progress of each cluster and server role.

Task Details

Summary

Task Status: Successful Submission Time: Dec 11, 2019, 20:25:32 Submitter: aliyuntest

Duration: 12 minutes Task Description: RemoveMachine: [iZh5i05w9770q3zmqltbdZ', 'iZh5i066934zp0o5i54mzZ', 'iZh5i05w9770q3zmqltbcZ', 'iZh5i05w9770q3z...

Server Role: All

Included Clusters

Clusters	Region	Status	Progress	Start Time	Actions
ec17	cn-	Successful	Build — Change	Dec 11, 2019, 20:25:32	View Version Differences Operation Log

total 1 items < 1 > 10/10 Page Go to 1 Page

Change Details | Clusters: ec17

Service Upgrade (8) Machine Change (4)

Server Role	Services	Upgrade Type	Status	Progress	Actions
rds-hbase.DbHBase#	rds-hbase	Configuration Change	Successful	Download — Upgrade	Details
rds-hbase.DbInit#	rds-hbase	Configuration Change	Successful	Download — Upgrade	Details
rds-hbase.InitCluster#	rds-hbase	Configuration Change	Successful	Download — Upgrade	Details

5.3.2.10 Reports

5.3.2.10.1 View reports

The Reports module allows you to view the statistical data.

Context

You can view the following reports on Apsara Infrastructure Management Framework.

- System reports: default and common reports in the system.
- All reports: includes the system reports and custom reports.

Procedure

1. [Log on to Apsara Infrastructure Management Framework.](#)

2. In the left-side navigation pane, choose **Reports**. On the Reports page, click **Go** to open the target page.

Report	Group	Status	Public	Created By	Published At	Actions
XDS Instance Metric Info	Tianjimon	Published	Public	admin	Published at : 11/13/19, 23:48:28 Created at : 11/13/19, 23:48:28	Add to Favorites Request Group Permission
Alert Status Profile	Tianjimon	Published	Public	admin	Published at : 10/30/19, 13:14:46 Created at : 10/30/19, 13:14:46	Add to Favorites Request Group Permission
Server Role Action Statuses	Tianji	Published	Public	admin	Published at : 10/30/19, 13:14:46 Created at : 10/30/19, 13:14:46	Add to Favorites Request Group Permission
Machine and Server Role Statuses	Tianji	Published	Public	admin	Published at : 10/30/19, 13:14:46 Created at : 10/30/19, 13:14:46	Add to Favorites Request Group Permission

For more information about the report descriptions, see the following table.

Item	Description
Report	<p>The report name.</p> <p>Move the pointer over the down-arrow button next to Report to search for reports by report name.</p>
Group	<p>The group to which the report belongs.</p> <p>Move the pointer over the down-arrow button next to Group to filter reports by group name.</p>
Status	<p>Indicates whether the report is published.</p> <ul style="list-style-type: none"> Published Not published
Public	<p>Indicates whether the report is public.</p> <ul style="list-style-type: none"> Public: All of the logon users can view the report. Not public: Only the current logon user can view the report.
Created By	The person who creates the report.
Published At	The time when the report is published and created.
Actions	Click Add to Favorites to add this report to your favorites. Then, you can view the report by choosing Reports > Favorites in the top navigation bar.

3. Optional: Enter the name of the report that you are about to view in the search box.
4. Click the report name to go to the corresponding report details page.

For more information about the reports, see Appendix.

5.3.2.10.2 Add a report to favorites

You can add common reports to favorites. Then, find them quickly on the Favorites page.

Procedure

1. [Log on to Apsara Infrastructure Management Framework.](#)
2. In the left-side navigation pane, choose **Reports**. On the Reports page, click **Go** to open the target page.
3. Enter the name of the report that you are about to add to favorites in the search box.
4. At the right of the report, click **Add to Favorites** in the **Actions** column.
5. In the displayed **Add to Favorites** dialog box, enter tags for the report.
6. Click **Add to Favorites**.

5.3.2.11 Tools

5.3.2.11.1 Machine tools

The Machine Tools module guides operations personnel to perform Operation & Maintenance (O&M) operations in common scenarios.

Procedure

1. [Log on to Apsara Infrastructure Management Framework.](#)
2. In the left-side navigation pane, choose **Tools > Operation Tools > Machine Tools**. On the Machine Tools page, click **Go** to open the target page.
3. Select the operation scene according to actual situations.

Operation scene	Description	Action
Scene 1: NC Scale-out (with existing machines)	Scales out an SRG of the worker type.	Select a target cluster and a target SRG. Select the machines to be scaled out in the left-side section and then click Select> to add them to the right-side section. Click Submit and then click Confirm in the displayed dialog box.

Operation scene	Description	Action
Scene 2: Host Scale-out (with existing machines)	Scales out the DockerHost #Buffer of an Apsara Infrastructure Management Framework cluster.	Select a target cluster. Select the machines to be scaled out in the left-side section and then click Select> to add them to the right-side section. Click Submit and then click Confirm in the displayed dialog box.
Scene 3: NC Scale-in	Scales in an SRG of the worker type.	Select a target cluster and a target SRG. Select the machines to be scaled in in the left-side section and then click Select> to add them to the right-side section. Click Submit and then click Confirm in the displayed dialog box.
Scene 4: Host Scale-in	Scales in the DockerHost #Buffer of an Apsara Infrastructure Management Framework cluster.	Select a target cluster. Select the machines to be scaled in in the left-side section and then click Select> to add them to the right-side section. Click Submit and then click Confirm in the displayed dialog box.
Scene 5: VM Migration	Migrates virtual machines (VMs) from a host to another host.	Select a source host and a destination host. Select the VMs to be migrated in the left-side section and then click Select> to add them to the right-side section. Click Submit and then click Confirm in the displayed dialog box.
Scene 6: Host Switching	Switches from a standby host to a primary host.	Select a source host and a destination host. Click Submit and then click Confirm in the displayed dialog box.

5.3.2.11.2 IDC shutdown

If you are about to maintain the data center or shut down all of the machines in the data center, you must shut down the data center.

Prerequisites

**Warning:**

This is a high-risk operation, so proceed with caution.

Procedure

1. [Log on to Apsara Infrastructure Management Framework.](#)
2. In the left-side navigation pane, choose **Tools > IDC Shutdown**, and then click **Go** to open the target page.
3. On the **Clusters Shutdown** page, click **Start Shutdown** to shut down all of the machines in the data center with one click.

5.3.2.11.3 View the clone progress

This topic describes how to go to the OS Provision console (Corner Stone) by using Apsara Infrastructure Management Framework, which allows you to know the progress, status, and errors of the machine installation.

Prerequisites

You have obtained the username and password of the OS Provision console from the delivery personnel.

Context

Apsara Infrastructure Management Framework provides a quick entry of the OS Provision console, which allows you to view the machine installation details. The OS Provision console allows you to view the machine clone details and then you can know the progress and status of the machine installation and locate the installation faults.

Procedure

1. [Log on to Apsara Infrastructure Management Framework.](#)
2. In the left-side navigation pane, choose **Tools > Clone Progress**.
3. On the logon page of the Corner Stone, enter the **Username** and **Password**, and then click **Submit**.

5.3.2.12 Metadata operations

In this version, you can only use command lines to perform metadata operations.

5.3.2.12.1 Common parameters

Common parameters consist of the common request parameters and the common response parameters.

Common request parameters

Common request parameters are request parameters that you must use when you call each API.

Table 5-8: Parameter descriptions

Name	Type	Required	Description
Action	String	Yes	The API name. For more information about the valid values, see APIs on the control side and APIs on the deployment side .

Common response parameters

Each time you send a request to call an API, the system returns a unique identifier, regardless of whether the call is successful.

Table 5-9: Parameter descriptions

Name	Type	Required	Description
RequestID	String	Yes	The request ID. The request ID is returned, regardless of whether the API call is successful.
Code	String	No	The error code.

Name	Type	Required	Description
Message	String	No	The reason of failure , which appears when the API call fails.
Result	The type varies with the request, which is subject to the returned result of the specific API.	No	The request result , which appears when the API call is successful.

**Note:**

- If the API call is successful, RequestID is returned and the HTTP return code is 200.
- If the API call fails, RequestID, Code, and Message are returned and the HTTP return code is 4xx or 5xx.

Instance types

```
{
  "rds.mys2.small":{
    "cpu":2,
    "memory":4096,
    "disk":51200,
    "max_connections":60
  },
  "rds.mys2.mid":{
    "cpu":4,
    "memory":4096,
    "disk":51200,
    "max_connections":150
  },
  "rds.mys2.standard":{
    "cpu":6,
    "memory":4096,
    "disk":51200,
    "max_connections":300
  },
  "rds.mys2.large":{
    "cpu":8,
    "memory":7200,
    "disk":102400,
    "max_connections":600
  },
  "rds.mys2.xlarge":{
    "cpu":9,
    "memory":12000,
    "disk":204800,
    "max_connections":1500
  },
  "rds.mys2.2xlarge":{
    "cpu":10,
    "memory":20000,
```

```
"disk":512000,  
"max_connections":2000  
}  
}
```

5.3.2.12.2 Access APIs

This topic describes how to access APIs on the control side and the deployment side.


Procedure

1. [Log on to Apsara Infrastructure Management Framework.](#)
2. In the left-side navigation pane, choose **Operations > Machine Operations**.
3. Select a project or enter the cluster name or machine name to search for the corresponding machine.

4. Access APIs.

- Access an API on the control side
 - a. Find the machine that you are about to access and then click **Terminal** in the **Actions** column to log on to the machine.
 - b. In the command window, enter the following command and then press Enter to obtain the intranet-domain.

```
grep 'intranet-domain' /cloud/app/tianji/TianjiClient#/service_manager/current/conf.global/kv.json
```



- c. You can log on to the API on the control side in the following ways. Here, take **ListInstance** as an example.

- Get request

```
curl 'xdb-master.xdb.{intranet-domain}:15678? Action=ListInstance'
```

- Post request

```
curl 'xdb-master.xdb.{intranet-domain}:15678' -X POST -d '{"Action": "ListInstance"}
```

- Access an API on the deployment side
 - a. Find the machine that you are about to access and record the IP address in the Hostname column.
 - b. You can log on to the API on the deployment side in the following ways. Here, take **CheckState** as an example.

Assume that the IP address of the target machine is 127.0.0.1.

- Get request

```
curl '127.0.0.1:18765? Action=CheckState&Port=3606'
```

- Post request

```
curl '127.0.0.1:18765' -X POST -d '{"Action": "CheckState", "Port": 3606}'
```

5.3.2.12.3 APIs on the control side

5.3.2.12.3.1 DescribeInstance

Views instances.

Description

Views the detailed information of an instance.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: DescribeInstance
InstanceName	String	Yes	The instance name.

Response parameters

For more information about the common response parameters, see [Common response parameters](#).

Name	Type	Required	Description
InstanceID	Integer	Yes	The instance ID.
InstanceName	String	Yes	The instance name.
Domain	String	Yes	The domain name.
Port	Integer	Yes	The instance port.
PaxosPort	Integer	Yes	The communication port between instance nodes.
InstanceDir	String	Yes	The instance directory.
Level	String	Yes	The instance specifications.
User	String	Yes	The username.
Password	String	Yes	The password.

Name	Type	Required	Description
Config	String	No	The custom my.cnf configuration of the instance, which is in the JSON format.
LeaderIP	String	No	The IP address of the primary node.
ActionName	String	Yes	The action name.
ActionStatus	String	Yes	The action status.
Description	String	Yes	The description.
IsDeleted	Integer	No	Whether the instance is deleted. 0 indicates No and 1 indicates Yes.
NodeList	[]NodeInfo	Yes	The information of the instance nodes.

The structure of NodeInfo is as follows.

Name	Type	Required	Description
InstanceID	Integer	Yes	The instance ID.
InstanceName	String	Yes	The instance name.
IP	String	Yes	The IP address of the instance node.
NodeID	Integer	Yes	The ID of the instance node.
ActionName	String	Yes	The action name.
ActionStatus	String	Yes	The action status.
Description	String	Yes	The description.
IsDeleted	Integer	No	Whether the node is deleted. 0 indicates No and 1 indicates Yes.

Examples

Sample requests

```
curl 'xdb-master.xdb.env8c-inc.com:15678? Action=DescribeInstance&InstanceName=xdb-meta'
```

Sample responses

```
{
  "Result": {
    "ActionName": "",
    "Level": "rds.mys2.standard",
    "InstanceID": 1,
    "LeaderIP": "10.39.XX.XX",
    "Config": "{}",
    "Description": "",
    "ActionStatus": "",
    "Domain": "xdb-meta.xdb.env8c-inc.com",
    "PaxosPort": 11606,
    "InstanceName": "xdb-meta",
    "User": "xdb",
    "Password": "xdb",
    "Port": 3606,
    "IsDeleted": 0,
    "InstanceDir": "/apsarapangu/disk1/xdb/xdb_instance_3606",
    "NodeList": [
      {
        "ActionStatus": "",
        "ActionName": "",
        "Description": "",
        "InstanceID": 1,
        "IP": "10.38.XX.XX",
        "InstanceName": "xdb-meta",
        "NodeID": 1,
        "IsDeleted": 0
      },
      {
        "ActionStatus": "",
        "ActionName": "",
        "Description": "",
        "InstanceID": 1,
        "IP": "10.39.XX.XX",
        "InstanceName": "xdb-meta",
        "NodeID": 2,
        "IsDeleted": 0
      },
      {
        "ActionStatus": "",
        "ActionName": "",
        "Description": "",
        "InstanceID": 1,
        "IP": "10.39.XX.XX",
        "InstanceName": "xdb-meta",
        "NodeID": 3,
        "IsDeleted": 0
      }
    ]
  },
  "RequestID": "3CFCBA07-3D87-4A99-B8C1-E861A7D1A573"
}
```

```
}
```

5.3.2.12.3.2 ListInstance

Lists instances.

Description

Lists the basic information of instances.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: ListInstance

Response parameters

For more information about the common response parameters, see [Common response parameters](#).

Name	Type	Required	Description
InstanceNames	String	Yes	The list of instance names.

Examples

Sample requests

```
curl 'xdb-master.xdb.env8c-inc.com:15678? Action=ListInstance'
```

Sample responses

```
{
  "Result": {
    "InstanceNames": [
      "xdb-meta",
      "xdb-instance-1",
      "xdb-instance-2",
      "xdb-instance-3"
    ]
  },
  "RequestID": "A921B8C7-C833-417C-B46A-E0CE129EBE48"
```

```
}
```

5.3.2.12.3.3 CreateInstance

Creates an instance.

Description

Creates an instance. This is an asynchronous task. You can view the task result by calling the DescribeTaskProgress API based on the RequestID in the responses.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: CreateInstance
InstanceName	String	Yes	The instance name.
User	String	Yes	The username.
Password	String	Yes	The password.
Level	String	Yes	Instance types
Config	String	No	The custom my.cnf configuration of the instance, which is in the JSON format. The key must be the same as the value of the field in my.cnf, which is of the string type.

Response parameters

[Common response parameters](#)

Examples

Sample requests

```
curl 'xdb-master.xdb.env8c-inc.com:15678? Action=CreateInstance&InstanceName=xdb-instance-1&User=admin&password=xdb&Level=rds.mys2.small'
```

Sample responses

```
{
  "Result": "Task has created, you can use api(DescribeTaskProgress) to get task progress",
  "RequestID": "8BCB3B39-6140-459F-B283-F83C03ADC3CA"
}
```

5.3.2.12.3.4 DeleteInstance

Deletes an instance.

Description

Deletes an instance. This is an asynchronous task. You can view the task result by calling the DescribeTaskProgress API based on the RequestID in the responses.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: DeleteInstance
InstanceName	String	Yes	The instance name.

Response parameters

[Common response parameters](#)

Examples

Sample requests

```
curl '127.0.0.1:15678? Action=DeleteInstance&InstanceName=xdb-instance-1'
```

Sample responses

```
{
```

```
"Result": "Task has created, you can use api(DescribeTaskProgress) to get task progress
.",
"RequestID": "9C40CCB3-4FAB-4242-9B87-792E8154E5CD"
}
```

5.3.2.12.3.5 RestartInstance

Restarts an instance.

Description

Restarts an instance. This is an asynchronous task. You can view the task result by calling the DescribeTaskProgress API based on the RequestID in the responses.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: RestartInstance
InstanceName	String	Yes	The instance name.

Response parameters

[Common response parameters](#)

Examples

Sample requests

```
curl 'xdb-master.xdb.env8c-inc.com:15678? Action=RestartInstance&InstanceName=xdb-
instance-2'
```

Sample responses

```
{
  "Result": "Task has created, you can use api(DescribeTaskProgress) to get task progress
.",
  "RequestID": "47277A23-5FFE-4A46-B65F-E6F2569F44E5"
}
```

```
}
```

5.3.2.12.3.6 UpgradeInstance

Performs a minor upgrade of an instance.

Description

Performs a minor upgrade of an instance. This is an asynchronous task. You can view the task result by calling the DescribeTaskProgress API based on the RequestID in the responses .

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: UpgradeInstance
InstanceName	String	Yes	The instance name.

Response parameters

[Common response parameters](#)

Examples

Sample requests

```
curl 'xdb-master.xdb.env8c-inc.com:15678? Action=UpgradeInstance&InstanceName=xdb-instance-2'
```

Sample responses

```
{
  "Result": "Task has created, you can use api(DescribeTaskProgress) to get task progress",
  "RequestID": "95E8B098-B04A-4BCA-BEBE-DA1D11BBAD4A"
}
```

5.3.2.12.3.7 DescribeTaskProgress

Views the task progress.

Description

Views the task progress.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value : DescribeTaskProgress
RequestID	String	Yes	The request ID.

Response parameters

For more information about the common response parameters, see [Common response parameters](#).

Name	Type	Required	Description
Progress	String	Yes	The instance progress, including pending, doing, done, and failed.
Description	String	Yes	The description of the instance progress .

Examples

Sample requests

```
curl 'xdb-master.xdb.env8c-inc.com:15678? Action=DescribeTaskProgress&RequestID=47277A23-5FFE-4A46-B65F-E6F2569F44E5'
```

Sample responses

```
{
  "Result": {
    "Progress": "done",
    "Description": "Success"
  },
  "RequestID": "AC535130-F40E-4D45-BC05-0F45C8473346"
```



```
}
```

5.3.2.12.3.8 ChangeLeaderTo

Changes the leader role of an instance to another node.

Description

Changes the leader role of an instance to another node.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: ChangeLeaderTo
InstanceName	String	Yes	The instance name.
IP	String	Yes	The IP address of the machine where the new leader node is located.

Response parameters

[Common response parameters](#)

Examples

Sample requests

```
curl 'xdb-master.xdb.env8c-inc.com:15678? Action=ChangeLeaderTo&InstanceName=xdb-instance-1&IP=10.39.XX.XX'
```

Sample responses

```
{
  "Result": "Success",
  "RequestID": "37638DE5-14C1-4D2E-984F-FEA1F29C9F84"
```

```
}
```

5.3.2.12.3.9 ModifyInstanceLevel

Modifies the instance specifications.

Description

Modifies the instance specifications. This is an asynchronous task. You can view the task result by calling the DescribeTaskProgress API based on the RequestID in the responses.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: ModifyInstanceLevel
InstanceName	String	Yes	The instance name.
Level	String	Yes	The new instance specifications.

Response parameters

[Common response parameters](#)

Examples

Sample requests

```
curl 'xdb-master.xdb.env8c-inc.com:15678? Action=ModifyInstanceLevel&InstanceName=xdb-instance-1&Level=rds.mys2.mid'
```

Sample responses

```
{
  "Result": "Task has created, you can use api(DescribeTaskProgress) to get task progress",
  "RequestID": "21B91211-BB09-4665-835D-9471A6F07F24"
```

```
}
```

5.3.2.12.3.10 DescribeLeader

Views the primary node information of an instance.

Description

Views the primary node information of an instance.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: DescribeLeader
InstanceName	String	Yes	The instance name.

Response parameters

For more information about the common response parameters, see [Common response parameters](#).

Name	Type	Required	Description
LeaderIP	String	Yes	The IP address of the primary node.
Port	Integer	Yes	The instance port.
User	String	Yes	The username.
Password	String	Yes	The password.

Examples

Sample requests

```
curl 'xdb-master.xdb.env8c-inc.com:15678? Action=DescribeLeader&InstanceName=xdb-meta'
```

Sample responses

```
{
  "Result": {
    "LeaderIP": "10.27.XX.XX",
    "Password": "xdb",
```

```
"Port": 3606,
"User": "xdb"
},
"RequestID": "2F05EE81-DC47-478E-9CA9-9AE8CA809151"
}
```

5.3.2.12.3.11 RecreateNode

Recreates an instance node.

Description

Uses other available nodes to recreate an instance node by backup and recovery. This is an asynchronous task. You can view the task result by calling the DescribeTaskProgress API based on the RequestID in the responses.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: RecreateNode
InstanceName	String	Yes	The instance name.
IP	String	Yes	The IP address of the instance node to be recreated.

Response parameters

[Common response parameters](#)

Examples

Sample requests

```
curl 'xdb-master.xdb.env8c-inc.com:15678? Action=RecreateNode&InstanceName=xdb-
instance-1&IP=10.39.XX.XX'
```

Sample responses

```
{
  "Result": "Task has created, you can use api(DescribeTaskProgress) to get task progress
  ",
  "RequestID": "7F079E11-1DE9-4148-A9FA-683E4C58F9C2"
}
```

```
}
```

5.3.2.12.3.12 CreateDatabase

Creates a database and a user.

Description

Creates a database and a user.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: CreateDatabase
InstanceName	String	Yes	The instance name.
DBName	String	Yes	The database name.
User	String	Yes	The username.
Password	String	Yes	The password.

Response parameters

[Common response parameters](#)

Examples

Sample requests

```
curl 'xdb-master.xdb.env8c-inc.com:15678? Action=CreateDatabase&InstanceName=xdb-instance-1&DBName=xdb&User=admin&Password=xdb_password'
```

Sample responses

```
{
  "Result": "Success",
  "RequestID": "A2BEF74F-5C3A-4CEF-A2B8-C14C71E36569"
```

```
}
```

5.3.2.12.3.13 DeleteDatabase

Deletes a database.

Description

Deletes a database.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: DeleteDatabase
InstanceName	String	Yes	The instance name.
DBName	String	Yes	The name of the database to be deleted.

Response parameters

[Common response parameters](#)

Examples

Sample requests

```
curl 'xdb-master.xdb.env8c-inc.com:15678? Action=DeleteDatabase&InstanceName=xdb-instance-1&DBName=xdb'
```

Sample responses

```
{
  "Result": "Success",
  "RequestID": "23F75A0A-B1D6-4341-BD5B-1A5F3FD45848"
}
```

5.3.2.12.3.14 DeleteUser

Deletes a user.

Description

Deletes a user.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: DeleteUser
InstanceName	String	Yes	The instance name.
User	String	Yes	The username.
Host	String	No	The source address range. If not configured, the user account is deleted in all of the source addresses by default.

Response parameters

[Common response parameters](#)

Examples

Sample requests

```
curl 'xdb-master.xdb.env8c-inc.com:15678? Action=DeleteUser&InstanceName=xdb-instance-1&User=admin&Host=10.39.XX.XX'
```

Sample responses

```
{
  "Result": "Success",
  "RequestID": "6A82AFF6-2B4D-48EF-868D-BBA54667D846"
}
```

5.3.2.12.4 APIs on the deployment side

5.3.2.12.4.1 CheckHealth

Checks if an instance node is of the leader role and whether the status is readable and writeable.

Description

Checks if an instance node is of the leader role. An instance node is regarded as healthy only if it is of the leader role and is readable and writeable.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: CheckHealth
Port	Integer	Yes	The port of the instance node.

Response parameters

For more information about the common response parameters, see [Common response parameters](#).

Name	Type	Required	Description
health	Boolean	Yes	The health status.

Examples

Sample requests

```
curl '127.0.XX.XX:18765? Action=CheckHealth&Port=3606'
```

Sample responses

```
{
  "Result": {
    "health": true
  },
  "RequestID": "304B69CE-1566-4E87-B618-233F40238FFF"
}
```

```
{
  "Message": "{ \"health\": false }",
}
```



```
"Code": "NodeNotHealth",  
"RequestID": "E939DB9B-4337-4B1C-8680-F62BEDD645DC"  
}
```

5.3.2.12.4.2 CheckState

Checks whether the status of an instance node is normal.

Description

Checks whether the status of an instance node is normal. Generally, you have the following two situations:

- The node is of the leader role and is readable and writeable.
- The node is of the follower role and is readable.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: CheckState
Port	Integer	Yes	The port of the instance node.

Response parameters

For more information about the common response parameters, see [Common response parameters](#).

Name	Type	Required	Description
IP	String	Yes	The IP address of the instance node.
Port	Integer	Yes	The instance port.
Role	String	Yes	The role of the instance node.
Writable	String	Yes	Whether the instance node is writeable.
Readable	String	Yes	Whether the instance node is readable.

Name	Type	Required	Description
State	String	Yes	The status of the instance node. If the status is normal, the value is GOOD. Otherwise, the value is ERROR.

Examples

Sample requests

```
curl '127.0.XX.XX:18765? Action=CheckState&Port=3606'
```

Sample responses

```
{
  "Result": {
    "Readable": true,
    "State": "GOOD",
    "Role": "Follower",
    "Port": 3606,
    "IP": "10.39.XX.XX"
  },
  "RequestID": "45A59426-46D3-4709-8DD6-CD9F243336E0"
}
```

5.3.2.12.4.3 DescribeNodeStatus

Views the status of an instance node.

Description

Views the status of an instance node. A leader node is readable and writeable, while a follower node is readable.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: DescribeNodeStatus

Name	Type	Required	Description
Port	Integer	Yes	The port of the instance node. This parameter is required if the instance mode is single_machine.

Response parameters

For more information about the common response parameters, see [Common response parameters](#).

Name	Type	Required	Description
IP	String	Yes	The IP address of the instance node.
Port	Integer	Yes	The port of the instance node.
Role	String	Yes	The instance role.
Writeable	String	Yes	Whether the instance node is writeable.
Readable	String	Yes	Whether the instance node is readable.
ConnectionCount	Integer/String	Yes	The number of connections. If the retrieval fails, the value is unknown.
MaxConnectionCount	Integer/String	Yes	The maximum number of connections. If the retrieval fails, the value is unknown.
ConnectionPercent	Integer/String	Yes	The percentage of connections. If the retrieval fails, the value is unknown.
QPS	Integer/String	Yes	Queries per second (QPS). If the retrieval fails, the value is unknown.

Name	Type	Required	Description
CpuPercent	Integer/String	Yes	The CPU usage. If the retrieval fails, the value is unknown.
MemoryPercent	Integer/String	Yes	The memory usage. If the retrieval fails, the value is unknown.
DiskPercent	Integer/String	Yes	The disk usage. If the retrieval fails, the value is unknown.
State	String	Yes	The status of the instance node. If the status is normal, the value is GOOD. Otherwise, the value is ERROR.

Examples

Sample requests

```
curl '127.0.XX.XX:18765? Action=DescribeNodeStatus&Port=3606'
```

Sample responses

```
{
  "Result": {
    "CpuPercent": 2.74,
    "IP": "10.39.XX.XX",
    "Readable": true,
    "MemoryPercent": 56.13,
    "State": "GOOD",
    "Role": "Follower",
    "MaxConnectionCount": 500,
    "ActiveThreadCount": 34,
    "Writeable": false,
    "ConnectionCount": 37,
    "DiskPercent": 3.0,
    "ConnectionPercent": 7.4,
    "QPS": 15.95,
    "Port": 3606
  },
  "RequestID": "D18328B1-78A9-4F3E-BB2E-B27AB7683C19"
```

```
}
```

5.3.2.12.4.4 ListNode

Lists instance nodes.

Description

Lists the basic information of instance nodes.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: ListNode

Response parameters

For more information about the common response parameters, see [Common response parameters](#).

Name	Type	Required	Description
Nodes	String	Yes	The list of instance names.

Examples

Sample requests

```
curl '127.0.XX.XX:18765? Action=ListNode'
```

Sample responses

```
{
  "Result": {
    "Nodes": [
      "xdb-instance-1",
      "xdb-instance-2",
      "xdb-instance-3",
      "xdb-meta"
    ]
  },
  "RequestID": "3F7BB536-FA3F-4597-A3DF-E5830F5A3A21"
```

}

5.3.2.12.4.5 BackupNode

Backs up data of an instance node and transmits the data to a specified location (Use the nc command to transmit data to the port of a specified IP address).

Description

Backs up data of an instance node and transmits the data to a specified location.

Request parameters

For more information about the common request parameters, see [Common request parameters](#).

Name	Type	Required	Description
Action	String	Yes	The parameter specified by the system. Value: BackupNode
Port	Integer	Yes	The instance port.
TargetIP	String	Yes	The IP address of the target location.
TargetPort	Integer	Yes	The port of the target location.

Response parameters

[Common response parameters](#)

Examples

Sample requests

```
curl '127.0.XX.XX:18765? Action=BackupNode&Port=3606&TargetIP=10.39.XX.XX&TargetPort='
```

Sample responses

```
{
  "Result": "Success",
  "RequestID": "6A82AFF6-2B4D-48EF-868D-BBA54667D846"
}
```

5.3.2.13 Appendix

5.3.2.13.1 Project component info report

This report displays the name and status for each type of project components, including services, server roles, and machines.

Item	Description
Project	The project name.
Cluster	The name of a cluster in the project.
Service	The name of a service in the cluster.
Server Role	The name of a server role in the service.
Server Role Status	The running status of the server role on the machine.
Server Role Action	The action that the server role performs on the machine. Data is available only when Apsara Infrastructure Management Framework asks the server role to perform certain actions, such as rolling and restart actions.
Machine Name	The hostname of the machine.
IP	The IP address of the machine.
Machine Status	The running status of the machine.
Machine Action	The action that Apsara Infrastructure Management Framework asks the machine to perform, such as the clone action.

5.3.2.13.2 IP list

This report displays the IP addresses of physical machines and Docker applications.

IP List of Physical Machines

Item	Description
Project	The project name.
Cluster	The cluster name.
Machine Name	The hostname of the machine.
IP	The IP address of the machine.

IP List of Docker Applications

Item	Description
Project	The project name.
Cluster	The cluster name.

Item	Description
Service	The service name.
Server Role	The server role name.
Machine Name	The hostname of the machine.
Docker Host	The Docker hostname.
Docker IP	The Docker IP address.

5.3.2.13.3 Machine info report

This report displays the statuses of machines and server roles on the machines.

Machine Status

Displays all the machines currently managed by Apsara Infrastructure Management Framework and their corresponding statuses. In the **Global Filter** section at the top of the page, select the project, cluster, and machine from the **project**, **cluster**, and **machine** drop-down lists, and then click **Filter** on the right to filter the data.

Item	Description
Machine Name	The machine name.
IP	The IP address of the machine.
Machine Status	The machine status.
Machine Action	The action currently performed by the machine.
Machine Action Status	The action status.
Status Description	The description about the machine status.

Expected Server Role List

Select a row in the **Machine Status** section to display the corresponding information in this list.

Item	Description
Machine Name	The machine name.
Server Role	The name of the expected server role on the machine.

Abnormal Monitoring Status

Select a row in the **Machine Status** section to display the corresponding information in this list.

Item	Description
Machine Name	The machine name.
Monitored Item	The name of the monitored item.
Level	The level of the monitored item.
Description	The description of the monitored item contents.
Updated At	The updated time of the monitored item.

Server Role Version and Status on Machine

Select a row in the **Machine Status** section to display the corresponding information in this list.

Item	Description
Machine Name	The machine name.
Server Role	The server role name.
Server Role Status	The status of the server role.
Target Version	The expected version of the server role on the machine.
Current Version	The current version of the server role on the machine.
Status Description	The description about the status.
Error Message	The exception message of the server role.

Monitoring Status

Select a row in the **Machine Status** section to display the corresponding information in this list.

Item	Description
Machine Name	The machine name.
Server Role	The server role name.
Monitored Item	The name of the monitored item.
Level	The level of the monitored item.
Description	The description of the monitored item contents.

Item	Description
Updated At	The updated time of the monitored item.

5.3.2.13.4 Rolling info report

This report displays the running and completed rolling tasks and the task-related status.

Choose a rolling action

This list only displays the running rolling tasks. If no rolling task is running, no data is available in the list.

Item	Description
Cluster	The cluster name.
Git Version	The version of change that triggers the rolling task.
Description	The description about the change entered by a user when the user submits the change.
Start Time	The start time of the rolling task.
End Time	The end time of the rolling task.
Submitted By	The ID of the user who submits the change.
Rolling Task Status	The current status of the rolling task.
Submitted At	The time when the change is submitted.

Server Role in Job

Select a rolling task in the **Choose a rolling action** section to display the rolling status of server roles related to the selected task. If no rolling task is selected, the server role statuses of all historical rolling tasks are displayed.

Item	Description
Server Role	The server role name.
Server Role Status	The rolling status of the server role.
Error Message	The exception message of the rolling task.
Git Version	The version of change to which the rolling task belongs.
Start Time	The start time of the rolling task.

Item	Description
End Time	The end time of the rolling task.
Approve Rate	The proportion of machines that have the rolling task approved by the decider.
Failure Rate	The proportion of machines that have the rolling task failed.
Success Rate	The proportion of machines that have the rolling task succeeded.

Server Role Rolling Build Information

The source version and target version of each application under the server role in the rolling process.

Item	Description
App	The name of the application that requires rolling in the server role.
Server Role	The server role to which the application belongs.
From Build	The version before the upgrade.
To Build	The version after the upgrade.

Server Role Statuses on Machines

Select a server role in the **Server Role in Job** section to display the deployment status of this server role on the machine.

Item	Description
Machine Name	The name of the machine on which the server role is deployed.
Expected Version	The target version of the rolling.
Actual Version	The current version.
State	The status of the server role.
Action Name	The Apsara Infrastructure Management Framework action currently performed by the server role.
Action Status	The action status.

5.3.2.13.5 Machine RMA approval pending list

Some Apsara Infrastructure Management Framework actions (such as restart) on machines and server roles can be triggered by users, but this type of actions must be reviewed and approved. This report is used to process the actions that must be reviewed and approved.

Machine

Displays the basic information of pending approval machines.

Item	Description
Project	The project name.
Cluster	The cluster name.
Hostname	The hostname of the machine.
IP	The IP address of the machine.
State	The running status of the machine.
Action Name	The action on the machine.
Action Status	The status of the action on the machine.
Actions	The approval button.

Machine Serverrole

Displays the information of server roles on the pending approval machines.

Item	Description
Project	The project name.
Cluster	The cluster name.
Hostname	The hostname of the machine.
IP	The IP address of the machine.
Serverrole	The server role name.
State	The running status of the server role.
Action Name	The action on the server role.
Action Status	The status of the action on the server role.
Actions	The approval button.

Machine Component

Displays the hard disk information of pending approval machines.

Item	Description
Project	The project name.
Cluster	The cluster name.
Hostname	The hostname of the machine.
Component	The hard disk on the machine.
State	The running status of the hard disk.
Action Name	The action on the hard disk.
Action Status	The status of the action on the hard disk.
Actions	The approval button.

5.3.2.13.6 Registration vars of services

This report displays values of all service registration variables.

Item	Description
Service	The service name.
Service Registration	The service registration variable.
Cluster	The cluster name.
Update Time	The updated time.

5.3.2.13.7 Virtual machine mappings

Use the global filter to display the virtual machines of a specific cluster.

Displays the information of virtual machines in the cluster. Data is available only when virtual machines are deployed in the cluster.

Item	Description
Project	The project name.
Cluster	The cluster name.
VM	The hostname of the virtual machine.
Currently Deployed On	The hostname of the physical machine on which the virtual machine is currently deployed.
Target Deployed On	The hostname of the physical machine on which the virtual machine is expected to be deployed.

5.3.2.13.8 Service inspector report

Use the global filter to display the service inspection reports of a specific cluster.

Service Inspector: Data is available only for services with inspection configured.

Item	Description
Project	The project name.
Cluster	The cluster name.
Service	The service name.
Description	The contents of the inspection report.
Level	The level of the inspection report.

5.3.2.13.9 Resource application report

In the **Global Filter** section, select the project, cluster, and machine from the **project**, **cluster**, and **machine** drop-down lists and then click **Filter** on the right to display the corresponding resource application data.

Change Mappings

Item	Description
Project	The project name.
Cluster	The cluster name.
Version	The version where the change occurs.
Resource Process Status	The resource application status in the version.
Msg	The exception message.
Begintime	The start time of the change analysis.
Endtime	The end time of the change analysis.

Changed Resource List

Item	Description
Res	The resource ID.
Type	The resource type.
Name	The resource name.
Owner	The application to which the resource belongs.
Parameters	The resource parameters.

Item	Description
Ins	The resource instance name.
Instance ID	The resource instance ID.

Resource Status

Item	Description
Project	The project name.
Cluster	The cluster name.
Service	The service name.
Server Role	The server role name.
APP	The application of the server role.
Name	The resource name.
Type	The resource type.
Status	The resource application status.
Parameters	The resource parameters.
Result	The resource application result.
Res	The resource ID.
Reprocess Status	The status of the interaction with Business Foundation System during the VIP resource application.
Reprocess Msg	The error message of the interaction with Business Foundation System during the VIP resource application.
Reprocess Result	The result of the interaction with Business Foundation System during the VIP resource application.
Refer Version List	The version that uses the resource.
Error Msg	The exception message.

5.3.2.13.10 Statuses of project components

This report displays the status of all server roles in an abnormal status on machines of the project, and the monitoring information (alert information reported by the server role to Apsara Infrastructure Management Framework monitor) of server roles and machines.

Error State Component Table

Only displays the information of server roles that are not in GOOD status and server roles to be upgraded.

Item	Description
Project	The project name.
Cluster	The cluster name.
Service	The service name.
Server Role	The server role name.
Machine Name	The machine name.
Need Upgrade	Whether the current version reaches the final status.
Server Role Status	The current status of the server role.
Machine Status	The current status of the machine.

Server Role Alert Information

Select a row in the **Error State Component Table** section to display the corresponding information in the list.

Item	Description
Cluster	The cluster name.
Service	The service name.
Server Role	The server role name.
Machine Name	The machine name.
Monitored Item	The monitored item name of the server role.
Level	The alert level.
Description	The description about the alert contents.
Updated At	The updated time of the alert information.

Machine Alert Information

Select a row in the **Error State Component Table** section to display the corresponding information in the list.

Item	Description
Cluster	The cluster name.
Machine Name	The machine name.
Monitored Item	The monitored item name of the server role.
Level	The alert level.

Item	Description
Description	The description about the alert contents.
Updated At	The updated time of the alert information.

Service Inspector Information

Select a row in the **Error State Component Table** section to display the corresponding information in the list.

Item	Description
Cluster	The cluster name.
Service	The service name.
Server Role	The server role name.
Monitored Item	The monitored item name of the server role.
Level	The alert level.
Description	The description about the alert contents.
Updated At	The updated time of the alert information.

5.3.2.13.11 Relationship of service dependency

This report displays the dependencies among server roles. Use the global filter to display the data of a specific cluster in the list.

Item	Description
Project	The project name.
Cluster	The cluster name.
Service	The service name.
Server Role	The server role name.
Dependent Service	The service on which the server role depends.
Dependent Server Role	The server role on which the server role depends.
Dependent Cluster	The cluster to which the dependent server role belongs.
Dependency in Final Status	Whether the dependent server role reaches the final status.

5.3.2.13.12 Check report of network topology

This report checks if network devices and machines have wirecheck alerts.

Check Report of Network Topology

Checks if network devices have wirecheck alerts.

Item	Description
Cluster	The cluster name.
Network Instance	The name of the network device.
Level	The alert level.
Description	The description about the alert information.

Check Report of Server Topology

Checks if servers (machines) have wirecheck alerts.

Item	Description
Cluster	The cluster name.
Machine Name	The server (machine) name.
Level	The alert level.
Description	The description about the alert information.

5.3.2.13.13 Clone report of machines

This report displays the clone progress and status of machines.

Clone Progress of Machines

Item	Description
Project	The project name.
Cluster	The cluster name.
Machine Name	The machine name.
Machine Status	The running status of the machine.
Clone Progress	The progress of the current clone process.

Clone Status of Machines

Item	Description
Project	The project name.

Item	Description
Cluster	The cluster name.
Machine Name	The machine name.
Machine Action	The action performed by the machine, such as the clone action.
Machine Action Status	The status of the action performed by the machine.
Machine Status	The running status of the machine.
Level	Whether the clone action performed by the machine is normal.
Clone Status	The current status of the clone action performed by the machine.

5.3.2.13.14 Auto healing/install approval pending report

The list structure is the same as the machine RMA approval pending list, whereas this view is used for the approval during the installation. For more information, see [Machine RMA approval pending list](#).

5.3.2.13.15 Machine power on or off statuses of clusters

After a cluster starts or shuts down machines, you can view the related information in this report.

Cluster Running Statuses

If a cluster is starting or shutting down machines, the corresponding data is available in this list. No data indicates that no cluster has machines shut down.

Item	Description
Project	The project name.
Cluster	The cluster name.
Action Name	The startup or shutdown action that is being performed by the cluster.
Action Status	The status of the action.

Server Role Power On or Off Statuses

Displays the power on or off statuses of server roles in the cluster selected in the **Cluster Running Statuses** section.

Select a row in the **Cluster Running Statuses** section to display the information of the corresponding cluster in the list.

Item	Description
Cluster	The cluster name.
Server Role	The server role name.
Action Name	The startup or shutdown action that is being performed by the server role.
Action Status	The status of the action.

Statuses on Machines

Displays the running status of the selected server role on machines.

Select a row in the **Server Role Power On or Off Statuses** section to display the information of the corresponding server role in the list.

Item	Description
Cluster	The cluster name.
Server Role	The server role name.
Machine Name	The machine name.
Server Role Status	The running status of the server role.
Server Role Action	The action currently performed by the server role.
Server Role Action Status	The status of the action.
Error Message	The exception message.

Machine Statuses

Displays the running statuses of machines in the selected cluster.

Select a row in the **Statuses on Machines** section to display the information of the corresponding machine in the list.

Item	Description
Cluster	The cluster name.
Machine Name	The machine name.
IP	The IP address of the machine.
Machine Status	The running status of the machine.
Machine Action	The action currently performed by the machine.

Item	Description
Machine Action Status	The action status of the machine.
Error Message	The exception message.

6 Products

The Products module allows you to click operations and maintenance services of other products on the cloud platform and ISV access configurations to go to the corresponding page.

6.1 Product list

In the **Product List**, you can be redirected to the corresponding operations and maintenance page of a product or ISV page by using Single Sign-On (SSO) and redirection.

Prerequisites

To be redirected to the ISV page, make sure that the ISV access information is configured on the **ISV Access Configurations** page. For more information about how to configure the ISV access information, see [Configure the ISV access information](#).

Context

After logging on to Apsara Stack Operations (ASO), you can view operations and maintenance icons of different products and different ISV icons in the **Product List** based on your permissions. For example, an operations system administrator can view all the operations and maintenance components of the cloud platform.

The read and write permissions for product operations and maintenance are separated. Therefore, the system can dynamically assign different permissions based on different roles .

Procedure

1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **Products > Product List**.
3. In the **Product List**, you can view operations and maintenance icons of different products and different ISV icons based on your permissions.

6.2 ISV access configurations

The **ISV Access Configurations** module allows you to configure, modify, and delete the ISV access information.

6.2.1 Configure the ISV access information

You can configure the ISV access information in the system based on business needs. Then, you can access the corresponding ISV page by clicking the icon in the **Product List**.

Procedure

1. [Log on to Apsara Stack Operations](#).
2. In the left-side navigation pane, choose **Products > ISV Access Configurations**.
3. Click **Add** on the page.
4. On the displayed **Add** page, configure the ISV access information.

For more information about the configurations, see the following table.

Configuration	Description
Name	The name of the ISV to be accessed.
Key	Generally, enter an identifier related to the ISV business as the key.
Icon	Select the icon displayed in the Product List for the ISV to be accessed.
Level-one Category and Level-two Category	The category to which the ISV to be accessed belongs in the Product List .
Usage	The function of the ISV to be accessed.
Access Link	The access address of the ISV to be accessed.
Description	The description related to the ISV to be accessed.

5. Then, click **Add**.

Result

You can view the added ISV icon in **Products > Product List**. Click the icon and then you can be redirected to the corresponding page.

6.2.2 Modify the ISV access information

If the ISV information is changed, you can modify the ISV access information.

Procedure

1. [Log on to Apsara Stack Operations.](#)
2. In the left-side navigation pane, choose **Products > ISV Access Configurations**.
3. Optional: In the search box on the page, enter the ISV name and then click **Search**. Fuzzy search is supported.
4. Find the ISV whose access information is to be modified. Click **Modify** in the **Actions** column.
5. On the displayed **Modify** page, modify the name, key, icon, level-one category, level-two category, usage, access link, or description of the ISV.
6. Then, click **Modify**.

6.2.3 Delete the ISV access information

You can delete the ISV access information added in the system based on business needs.

Procedure

1. [Log on to Apsara Stack Operations.](#)
2. In the left-side navigation pane, choose **Products > ISV Access Configurations**.
3. Optional: In the search box on the page, enter the ISV name and then click **Search**. Fuzzy search is supported.
4. Find the ISV whose access information is to be deleted. Click **Delete** in the **Actions** column.
5. In the displayed dialog box, click **OK**.

Result

Then, the ISV information is not displayed in **Products > Product List**.

7 Log configurations

7.1 What is LogAgentconfig?

LogAgentconfig is a single-node service that is deployed on OPS1, and is one of the Apsara Stack Agility SE base modules. LogAgentconfig delivers and updates log collection configurations.

LogAgentconfig serves as a configuration delivery service on the Log Service client. After the log directories, name of the log file to be collected, Logtail configuration in full regex mode, and log parsing configuration are committed, LogAgentconfig delivers log collection configurations to base modules. After the configurations are delivered, the collected logs are written to the Kafka service. Then, the logs in Kafka are consumed by Logstash and stored in Elasticsearch. Finally, you can view logs in Kibana.

7.2 Log on to the LogAgentconfig console

This topic describes how to log on to the LogAgentconfig console.

Prerequisites

Before you log on to the LogAgentconfig console, confirm with the deployment personnel that the following requirements have been met:

- LogAgentconfig is deployed on the OPS1 server in the current deployment environment and reaches the desired state.
- logservicelite-Kafka and logservicelite-elk reach the desired state.

Procedure

1. Obtain the URL used to access the LogAgentconfig console by using Apsara Infrastructure Management Framework.

**Note:**

This topic describes how to Obtain the URL used to access the LogAgentconfig console by using Apsara Infrastructure Management Framework. If you have obtained the IP

address of the OPS1 server, append port number 8888 to the IP address to obtain the URL of the LogAgentconfig console. Example: `http://<OPS1 IP address>:8888`.

a) Log on to the Apsara Infrastructure Management Framework console.

For more information about how to log on to the new version and the old version of the Apsara Infrastructure Management Framework console, see **Operations tools > Apsara Infrastructure Management Framework > New version**, or **Operations tools > Apsara Infrastructure Management Framework > Old version** in the “**Log on to Apsara Infrastructure Management Framework**” section of Apsara Stack Agility SE Operations and Maintenance Guide . This topic describes how to log on to the LogAgentconfig console by using the new version of the Apsara Infrastructure Management Framework console.

b) In the left-side navigation pane, click **Reports**.

c) Find and click **Resource Application Report** on the All Reports page.

d) In the **Resource Status** section, click the More icon on the Service column, enter `logservicelite-logagentconfig`, and click Apply Filter.

The screenshot shows the 'Resource Application Report' page in the Apsara Infrastructure Management Framework console. The top navigation bar includes 'Home', 'Operations', 'Tasks', 'Reports', 'Management', and 'Monitoring'. The 'Reports' tab is selected. Below the navigation bar, the page title is 'Resource Application Report'. Under the 'Details' section, there are two radio buttons: 'Formatted Value' (selected) and 'Original Value'. A JSON configuration is displayed in a code block:

```
{
  "domain": "logagentconfig.1234567890.com",
  "https_proxy": "false",
  "ip": "192.168.1.1",
  "name": "logagentconfig"
}
```

Below the JSON configuration, there is a table with three columns: 'paas', 'mock-cluster...', and 'c73a881e5fa...'. The table contains three rows of data, each showing a status of 'Cannot get s...' and a timestamp of '04/03/20, 23:...'.

paas	mock-cluster...	c73a881e5fa...	Cannot get s...	04/03/20, 23:...	04/03/20, 23:...
paas	mock-cluster...	79dfab93344...	Cannot get s...	04/07/20, 13:...	04/07/20, 13:...
paas	mock-cluster...	91b263528a...	Cannot get s...	04/07/20, 13:...	04/07/20, 13:...

e) Append port number 8888 to the domain name that you obtained in the preceding step to obtain the URL of the LogAgentconfig console. Example: `http://Logagentconfig.example.com:8888`.

2. Enter the URL in the address bar of your browser, and press the Enter key to go to the logon page of the LogAgentconfig console.

7.3 Configure log collection

This topic describes how to configure log collection for base modules.

Procedure

1. Log on to the LogAgentconfig console.
2. In the **Configure** section, configure the parameters of the server role from which logs will be collected.

Parameter	Description
ConfigureName	The name of the configuration file. The name must be unique. Otherwise, the configuration file fails to be delivered.
ServiceName	The name of the service to which the target server role belongs.
ServiceRole	The name of the service role from which logs will be collected
ClusterName	The name of the cluster to which the target server role belongs.

Configure:

ConfigureName: ServiceName: ServiceRole: ClusterName:

ConfigureInfo

Configure Sample

```
{
  "logPath": "/www/logsss",
  "filePattern": "*.log",
  "logType": "common_reg_log",
  "logBeginReg": "\\d+-\\d+-\\d+\\s\\d+:\\d+:\\d+\\s.*",
  "keys": [
    "time.level.workerId.organizationId.resourcearoundId"
  ]
}
```

Machine Info

	Id	hostName	ip	sshKeygenState	user	
	0	a56...	...	Privacy free login	<input type="text"/>	<input type="text"/>
	1	a56...	...	Privacy free login	<input type="text"/>	<input type="text"/>

Showing 1 to 2 of 2 rows

Commit

After you configure the preceding parameters, information about the machine where the server role resides is displayed in the **Machine Info** section.

3. Enter the collection configuration information in the **ConfigureInfo** section, as shown in the Configure Sample section.

Based on the information, the system automatically generates the configuration file for log collection.

4. In the **Machine Info** section, select the machines to which you want to deliver the configuration file. Then, enter the username and password, and click **Check**.

**Note:**

You can enter a machine name in the search bar to search for the required machine.

The system checks whether the username and password are correct, and provides the check result.

5. In the message that appears, click **OK**.

6. Click **Commit**.

The entered information is delivered to a backend service that dynamically generates the configuration file for log collection to be delivered to the specified machine. The entered information includes the configuration name and server role information specified in the **Configure** section, the configuration information specified in the **ConfigureInfo** section, and the machine information selected in the **Machine Info** section.

After the configurations are delivered, the configuration information appears in the **Configure History** section.

7. After configurations are delivered, you can log on to Kibana Log O&M platform to view the log information collected.

For more information about how to view log information on the Kibana Log O&M platform, see the content in the "Kibana Log O&M" section of Apsara Stack Agility SE Operations and Maintenance Guide .

8 Log O&M

8.1 Kibana Log O&M

8.1.1 Overview of the Kibana log O&M platform

Kibana 7.1 is an open-source analytics and visualization platform. Logs for Apsara Stack Agility SE services such as ApsaraDB for RDS, Xnet2, Asapi, and POP are accessible to Elasticsearch, Logstash, and Kibana (ELK). You can use Kibana to view and retrieve related logs.

This topic describes only the common features of Kibana 7.1 for daily O&M. For more information, visit [Kibana Guide](#).

8.1.2 Log on to the Kibana log O&M platform

This topic describes how to log on to the Kibana log O&M platform.


Prerequisites

- ASO access address in the format of `http://region-id.aso.intranet-domain-id.com`.
- Google Chrome browser (recommended).

Procedure

1. Open the browser.

2. Enter the ASO access address `http://region-id.aso.intranet-domain-id.com` in the address bar and then press Enter.

A screenshot of the ASO Log On interface. It features a dark blue background with the title 'Log On' in white. Below the title, there are two input fields: the first is labeled 'Enter a user name' with a user icon, and the second is labeled 'Enter the password' with a lock icon. At the bottom, there is a prominent blue button labeled 'Log On'.**Note:**

You can select the language from the drop-down list in the upper-right corner to change the language of ASO.

3. Enter the correct username and password.

**Note:**

Obtain the username and password used to log on to ASO from the deployment personnel or the administrator.

- The system has three default users:
 - Security officer: manages other users or roles.
 - Auditor officer: views audit logs.
 - System administrator: used for other functions except those of the security officer and auditor officer.
- You must modify the password of your username as instructed when you log on to ASO for the first time. To improve security, the password must be 10-20 characters long and can contain English uppercase/lowercase letters (A-Z or a-z), numbers (0-9), and special characters, such as exclamation points (!), at signs (@), number signs (#), dollar signs (\$), and percent signs (%), which meets the minimum complexity requirements.

4. Click **Log On** to log on to ASO.

5. In the left-side navigation pane, click **Products**.
6. In the **Apsara Stack O&M** section, click **Kibana Log O&M**.

8.1.3 Quick start


8.1.3.1 Create index patterns

You must create index patterns before you can view and retrieve logs.


Context

An index pattern can identify one or more indexes. Kibana allows you to search for indexes that match a specified index pattern.

Procedure

1. [Log on to the Kibana log O&M platform](#).
2. In the left-side navigation pane, click the  icon.

3. In the **Kibana** section, click **Index Patterns**.



Note:

When you create an index pattern for the first time, the **Create index pattern** page appears automatically. To create more index patterns, you must click **Create index pattern** in the upper-left corner of the page to open the **Create index pattern** page.

4. In the **Index pattern** field, enter the name of the index pattern as prompted.

After you enter an index pattern name, the system matches indexes based on the index pattern. To match system indexes, turn on **Include system indices** in the upper-right corner of the page.



Note:

To match a specified index, you can set the index pattern name to the index name without using wildcards.

5. Click **Next step**.

6. On the right of **Time Filter field name**, click **Refresh**. Select a time field from the **Time Filter field name** drop-down list for visualization.



Note:

- Before you select a time field from the **Time Filter field name** drop-down list, you can click **Refresh** in the upper-right corner.

- If the time field is not contained in the matched indexes, this option is not required.

Create index pattern

Kibana uses index patterns to retrieve data from Elasticsearch indices for things like visualizations.

☐ Include system indices

Step 2 of 2: Configure settings

You've defined `*-*` as your index pattern. Now you can specify some settings before we create it.

Time Filter field name

Refresh

@timestamp

The Time Filter will use this field to filter your data by time. You can choose not to have a time field, but you will not be able to narrow down your data by a time range.

[Show advanced options](#)

[< Back](#)
[Create index pattern](#)


- Optional: Click **Show advanced options**, and enter a custom index pattern ID as prompted.
- Click **Create index pattern**.

8.1.3.2 View data in documents


You can view the documents that match an index and all the data in the documents.

Procedure

- Log on to the Kibana log O&M platform.

2. In the left-side navigation pane, click the  icon.

The default index pattern is displayed below the filter bar. You can select an index pattern from the list as needed. Kibana matches the target indexes based on the specified index pattern.




3. In the **Available fields** list, move the pointer over a field, and click **add** to add the field to the **Selected fields** list.
4. You can add multiple fields. All documents that match the fields listed in **Selected fields** are displayed on the right side of the page.




Note:

If there is a field you do not want to view matches for, you can move the pointer over the field in the **Selected fields** list, and click **remove**. Alternatively, you can move the pointer over the field on the right side of the page, and click the Delete icon.



5. Click the Collapse icon in front of each document to view the details of each document.

You can view data in the **Table** and **JSON** formats.



6. When you view documents, you can perform the following operations:

- View a single document

You can click **View single document** to view a document on a new page. You can bookmark this page and share its link to enable direct access to the document.

- View surrounding documents

For some applications, you may need to view documents before and after a document. You can only view surrounding documents for index patterns that contain time-based events.

Click **View surrounding documents**. Documents listed before and after the specified document are displayed. The displayed documents are sorted by the time field specified in the index pattern configurations. If multiple documents have the same time field value, the documents are sorted in the internal order by default.

- Change the ordinal position of fields

Move the pointer over the name of the target field and click the Move icon behind the field name to move the field to the left or to the right.



Note:


Only index fields can be sorted.

Time	@topic	_index
> Apr 14, 2020 @ 13:57:44.394	Move column to the right	_log-2020.04.14
> Apr 14, 2020 @ 13:57:44.393		_log-2020.04.14
> Apr 14, 2020 @ 13:57:28.686		_log-2020.04.14
> Apr 14, 2020 @ 13:57:28.686		_log-2020.04.14
> Apr 14, 2020 @ 13:57:23.051		_log-2020.04.14
> Apr 14, 2020 @ 13:57:23.050		_log-2020.04.14
> Apr 14, 2020 @ 13:57:23.050		_log-2020.04.14

8.1.3.3 Filter data by using a time filter

A time filter allows you to search data generated within a specific time range. If a time field is configured for the selected index pattern, you can configure a time filter to filter data.

Procedure

1. [Log on to the Kibana log O&M platform.](#)
2. In the left-side navigation pane, click the  icon.

The default index pattern is displayed below the filter bar. You can select an index pattern from the list as needed. Kibana matches the target indexes based on the specified index pattern.

3. On the **Discover** page, configure a time filter.


By default, the time filter is set to the last 15 minutes. You can use the time selector to reset the time filter in the following ways:

- Click the field on the right of the time selector to set the start time and end time in sequence. On the **Absolute** tab, set a start time and end time. On the **Relative** tab, set a start time and end time relative to the current time. The relative time can be in the past or future.




Note:

To set the current time as the start time or end time, you can click **Set data and time to now** on the **Now** tab.



- Click the time selector icon. In the **Quick select** section, specify a time filter relative to the current time in years, months, weeks, days, hours, minutes, or seconds in the past or future. Click **Apply**.




- Click the time selector icon. In the **Commonly used** section, select the desired time from the listed options, including Today, This week, This month, This year, Today so far, Week to date, Month to date, and Year to date. Click **Apply**.
- Click the time selector icon. In the **Recently used date ranges** section, select a recently used filter. Click **Apply**.

After a time filter is configured, data that meets the specified conditions are displayed.

8.1.3.4 Filter data by using column charts


You can use column charts to filter data if a time field is configured for the index pattern.

Procedure

1. [Log on to the Kibana log O&M platform.](#)
2. In the left-side navigation pane, click the  icon.

The default index pattern is displayed below the filter bar. You can select an index pattern from the list as needed. Kibana matches the target indexes based on the specified index pattern.

3. In column charts on the right side of the page, you can click a chart and move the pointer to view the data distribution in a specific time range.




Note:

You can click a column chart multiple times to enlarge it.

8.1.3.5 Query data by using KQL

You can use the query syntax provided by Kibana Query Language (KQL) to query data.

Procedure

1. [Log on to the Kibana log O&M platform.](#)
2. In the left-side navigation pane, click the  icon.


The default index pattern is displayed below the filter bar. You can select an index pattern from the list as needed. Kibana matches the target indexes based on the specified index pattern.

3. In the **Filters** field, enter the fields to be queried.

When you enter the fields to be queried, you can select fields from the available fields, and then select filter conditions as prompted.

The following table describes the symbols of filtering conditions.

Symbol	Description
:	The field value must be the specified value.
.*	The field value can be in any format.
and	The field value must meet the specified two conditions.
or	The field value must meet one or more conditions.



4. Press the Enter key to query data.

8.1.4 Explore data

8.1.4.1 Open a saved search


You can open a saved search on the **Discover** page.


Prerequisites

Make sure that a saved search exists. For more information about how to save a search, see [Save a search](#).

Procedure

1. [Log on to the Kibana log O&M platform](#).

2. In the left-side navigation pane, click the  icon.
3. In the toolbar at the top of the page, click **Open**.
4. In the **Open Search** dialog box that appears, select a saved search.




After a saved search is opened, if the index pattern specified in the saved search is different from the selected index pattern, the index pattern specified by the saved search is used. The query statements of the saved search are also used.

8.1.4.2 View statistics for field data


In the field list, you can view the statistics of each field, including the number of documents that contain the field, top five values in the field, and percentage of each value in these documents.

Procedure

1. [Log on to the Kibana log O&M platform.](#)
2. In the left-side navigation pane, click the  icon.

The default index pattern is displayed below the filter bar. You can select an index pattern from the list as needed. Kibana matches the target indexes based on the specified index pattern.

3. In the **Available fields** list, click the name of the field that you want to view.




The following statistics are displayed below the field: the number of documents that contain the field, top five values in the field, and the percentage of each value in these documents.

4. Optional: For aggregatable fields, you can click **Visualization** to view and analyze the visualized data.

8.1.4.3 Filter by fields


You can add a field filter from the field list or document list, or you can manually add a field filter to filter documents that contain specific field values. You can also create a negative filter to exclude documents that contain the specified field values.

Add a filter from the field list

1. [Log on to the Kibana log O&M platform.](#)
2. In the left-side navigation pane, click the  icon.

The default index pattern is displayed below the filter bar. You can select an index pattern from the list as needed. Kibana matches the target indexes based on the specified index pattern.


3. In the **Available fields** list, click the name of the field for which you want to add a filter.




The statistics of the field are displayed.

4. You can perform the following operations:


- Add a positive filter for a field

Click the  icon next to a field value. Documents that contain the specified field value are displayed on the right side of the page.

- Add a negative filter for a field

Click the  icon next to a field value. Documents that do not contain the specified field value are displayed on the right side of the page.

Add a filter from the document list

1. [Log on to the Kibana log O&M platform.](#)
2. In the left-side navigation pane, click the  icon.

The default index pattern is displayed below the filter bar. You can select an index pattern from the list as needed. Kibana matches the target indexes based on the specified index pattern.

3. In the **Available fields** list, move the pointer over a field, and click **add** to add the field to the **Selected fields** list.

All documents that match the fields in the **Selected fields** list are displayed on the right side of the page.

4. Click the collapse icon in front of the target document to view all fields contained in the document.



The screenshot displays the Kibana Log O&M interface. At the top, there is a table with columns: Time, @topic, and _index. Below this, a document is expanded, showing a list of fields and their values. A red box highlights the 'Add' button (a magnifying glass icon) in the 'Available fields' list.

Time	@topic	_index
Apr 5, 2020 @ 21:38:38.076	[redacted]_log	[redacted]_log-2020.04.05

Expanded document


View surrounding documents

Table JSON


Field	Value
@timestamp	Apr 5, 2020 @ 21:38:38.076
@topic	[redacted]_log
@version	1
AK	[redacted]
AdditionalInfo	IsolationMessage=inner pop
AkProxy	[redacted]

5. You can perform the following operations:


- Add a positive filter for a field

Find the index field for which you want to add a filter, move the pointer over the field, and then click the  icon. Documents that contain the specified field value are displayed on the right side of the page.


- Add a negative filter for a field

Find the index field for which you want to add a filter, move the pointer over the field, and then click the  icon. Documents that do not contain the specified field value are displayed on the right side of the page.

- Query documents that contain a specific field


Find a field whose values are not empty and for which you want to add a filter, move the pointer over the field, and then click the  icon. Documents that contain the field are displayed on the right side of the page.

Add filters manually


1. [Log on to the Kibana log O&M platform.](#)
2. In the left-side navigation pane, click the  icon.

The default index pattern is displayed below the filter bar. You can select an index pattern from the list as needed. Kibana matches the target indexes based on the specified index pattern.

3. In the toolbar at the top of the page, click **Add filter**.



4. Select a field from the **Field** drop-down list, select an operator from the **Operator** drop-down list, and then enter a value in the **Value** field.



5. To create a custom label, turn on **Create custom label**, and enter the label information.
6. Click **Save**.


Then, the system queries information of the specified field.

8.1.4.4 Configure a refresh interval

When index data changes, results displayed on the **Discover** page may become obsolete. To avoid such problems, you can configure a refresh interval to periodically resubmit your searches to retrieve the latest results.


Procedure

1. [Log on to the Kibana log O&M platform.](#)

2. In the left-side navigation pane, click the  icon.

The default index pattern is displayed below the filter bar. You can select an index pattern from the list as needed. Kibana matches the target indexes based on the specified index pattern.

3. On the **Discover** page, click the Time Selector icon in the Kibana toolbar.



4. In the **Refresh every** field, enter a refresh interval. **0** indicates that the search results will not be refreshed.
5. Click **Start**.

After you configure a refresh interval, your searches will be periodically resubmitted based on the specified interval to refresh the search results.


8.1.4.5 Save a search

After you query, filter, or search for specific data, you can save the search as needed.

Procedure

1. For more information about how to query, filter and search for data, see [View data in documents](#), [Filter data by using a time filter](#), [Filter data by using column charts](#), or [Query data by using KQL](#).


2. In the toolbar at the top of the page, click **Save**.



8.1.5 Use development tools to retrieve data

You can also use development tools to retrieve data.

Procedure

1. [Log on to the Kibana log O&M platform.](#)
2. In the left-side navigation pane, click the  icon.
3. On the **Console** tab of the **Dev Tools** page, enter query statements to search for data that meets the specified conditions.

Example:

- Query all indexes: `GET /_cat/indices? pretty`
- Query the specified index content: `Get indexname/_search`
- Query indexes based on query statements:

```
Get /indexname/_doc/_search{
  "query":{
    "query_string":{
      "query":"condition"
      // The condition must be in the "field name: the data you want to search"
      format. You can use "and" to connect multiple queries.
      // Example: "query":"id:123 and name:Alice"
    }
  },
  "sort":{
    "@timestamp":{
      "order":"asc" // The sorting method.
    }
  },
  "from":?,"size": 100 //The number of logs to query each time.
```

}

8.1.6 Manage index patterns


8.1.6.1 Set the default index pattern


The first index pattern you create is automatically designated as the default pattern. You can click the star icon in the upper-right corner of the index pattern to reset the default pattern.


Prerequisites

An index pattern is created. For more information about how to create an index pattern, see [Create index patterns](#).

Procedure

1. [Log on to the Kibana log O&M platform](#).
2. In the left-side navigation pane, click the  icon.
3. In the **Kibana** section, click **Index Patterns**.
4. In the left-side index pattern list, select an index pattern that you want to set as the default pattern.



5. In the upper-right corner of the index pattern, click the  icon.

Result

After an index pattern is set as the default pattern, a star icon is displayed to the left of the default pattern name.

8.1.6.2 Delete index patterns



You can remove an index pattern from the list of Saved Objects in Kibana. After you delete an index pattern, you will not be able to restore field formatters, scripted fields, source filters, and field popularity data related to the index pattern.

Context

Deleting an index pattern will interrupt all visualizations, saved searches, and other saved objects that reference the pattern.

Deleting an index pattern will not remove any indexes or data documents from Elasticsearch.


Procedure

1. [Log on to the Kibana log O&M platform.](#)
2. In the left-side navigation pane, click the  icon.
3. In the **Kibana** section, click **Index Patterns**.
4. In the left-side navigation pane, select an index pattern to be deleted.
5. In the upper-right corner of the index pattern, click the  icon.
6. In the message that appears, click **Delete**.

8.1.7 Manage indexes

Index Management allows you to view index settings, mappings, and statistics and perform operations on indexes such as refreshing and freezing indexes, clearing the cache, and forcibly merging segments. Index Management also allows you to perform operations on multiple indexes at a time.

Procedure

1. [Log on to the Kibana log O&M platform.](#)
2. In the left-side navigation pane, click the  icon.

3. In the **Elasticsearch** section, click **Index Management**.

Indexes are listed on the right side of the page. By default, the index list does not contain rollup indexes and system indexes. To list these indexes, you can turn on **Include rollup indices** or **Include system indices**.

Index management

Update your Elasticsearch indices individually or in bulk.

☐ Include rollup indices

☐ Include system indices

Reload indices

<input type="checkbox"/>	Name	Health	Status	Primaries	Replicas	Docs count	Storage size
<input type="checkbox"/>		● green	open	9	1	85	1.2mb
<input type="checkbox"/>		● green	open	9	1	120	1.9mb
<input type="checkbox"/>		● green	open	9	1	300	1.2mb
<input type="checkbox"/>		● green	open	9	1	5860	6.4mb
<input type="checkbox"/>		● green	open	9	1	13217	64.2mb
<input type="checkbox"/>		● green	open	9	1	42362	183.7mb
<input type="checkbox"/>		● green	open	9	1	242	1.2mb

4. You can perform the following operations:

- View brief information about an index

In the right-side index list, click the name of the index that you want to view. You can view brief information about the index on the **Summary** tab.

- View index settings

In the right-side index list, select the index that you want to view, click **Manage index**, and then select **Show index settings** from the INDEX OPTIONS drop-down list. On the **Settings** tab that appears, view the configuration information of the index.

The screenshot shows the 'Index management' page. At the top, there's a header 'Index management' and a sub-header 'Update your Elasticsearch indices individually or in bulk.' To the right, there are two toggle switches: 'Include rollup indices' and 'Include system indices'. Below the header, there's a 'Manage index' button with a dropdown arrow. A dropdown menu is open, showing 'INDEX OPTIONS' with the following items: 'Show index settings', 'Show index mapping', 'Show index stats', 'Edit index settings', 'Close index', 'Force merge index', 'Refresh index', 'Clear index cache', 'Flush index', 'Freeze index', 'Delete index', and 'Add lifecycle policy'. In the background, a table of indices is visible with columns: Name, Primaries, Replicas, Docs count, and Storage size. The first row of the table is highlighted in blue.

Name	Primaries	Replicas	Docs count	Storage size
[blurred]	9	1	88	1.2mb
[blurred]	9	1	120	1.9mb
[blurred]	9	1	300	1.2mb
[blurred]	9	1	5860	6.4mb
[blurred]	9	1	13330	64.2mb
[blurred]	9	1	42362	183.7mb
[blurred]	9	1	242	1.2mb
[blurred]	9	1	55806	234.2mb
[blurred]	9	1	139	631.9kb

- View index mapping

In the right-side Index list, select the index that you want to view, click **Manage index**, and then select **Show index mapping** from the INDEX OPTIONS drop-down list. On the **Mapping** tab that appears, view the mapping information of the index.

- View index statistics

In the right-side index list, select the index that you want to view, click **Manage index**, and then select **Show index stats** from the INDEX OPTIONS drop-down list. On the **Stats** tab that appears, view the statistics of the index.

- Edit index settings

In the right-side Index list, select the index that you want to view, click **Manage index**, and then select **Edit index settings** from the INDEX OPTIONS drop-down list. On the **Edit settings** tab that appears, modify the index settings and click **Save**.

- Close indexes

When an index is closed, read and write operations are not allowed on the index. Closed indexes in clusters do not consume any resources other than disk space. If you reopen a closed index, it will go through the normal recovery process.

In the right-side index list, select one or more indexes to close, click **Manage index**, and then select **Close index** from the INDEX OPTIONS drop-down list.

The screenshot shows the 'Index management' interface. At the top, there's a title 'Index management' and a subtitle 'Update your Elasticsearch indices individually or in bulk.' To the right, there are two toggle switches: 'Include rollout indices' and 'Include system indices'. Below the title, there's a 'Manage indices' dropdown menu. The dropdown menu is open, showing a list of 'INDEXES OPTIONS': 'Close indices', 'Force merge indices', 'Refresh indices', 'Clear indices cache', 'Flush indices', 'Freeze indices', and 'Delete indices'. In the background, there's a table with columns: 'Name', 'Status', 'Type', 'Primary', 'Replicas', 'Docs count', and 'Storage size'. The table lists several indices, including 'c_trace_log-2' which is 'green' and 'open'.

- Forcibly merge indexes

You can forcibly merge an index by merging small files and clearing deleted files to reduce the number of segments in a shard. Only read-only indexes can be forcibly merged.

In the right-side index list, select one or more indexes, click **Manage index**, and then select **Force merge index** from the INDEX OPTIONS drop-down list.

- Refresh indexes

You can refresh indexes to write operations in the indexing buffer to the file system cache. This action is automatically performed once every second.

In the right-side index list, select one or more indexes, click **Manage index**, and then select **Refresh index** from the INDEX OPTIONS drop-down list.

**Note:**

We recommend that you do not manually refresh indexes because this may affect performance.

- Clear index cache

You can clear all caches related to indexes.

In the right-side index list, select one or more indexes, click **Manage index**, and then select **Clear index cache** from the INDEX OPTIONS drop-down list.

- Flush indexes

In the right-side index list, select one or more indexes to flush, click **Manage index**, and then select **Flush index** from the INDEX OPTIONS drop-down list.

- Freeze indexes

Frozen indexes are read-only indexes whose shards have been moved to disks to reduce memory usage. Frozen indexes can still be queried, but will take longer.

In the right-side index list, select one or more indexes to freeze, click **Manage index**, and then select **Freeze index** from the INDEX OPTIONS drop-down list.

- Delete indexes

When you delete an index, the index and all of its documents are deleted permanently.

In the right-side index list, select one or more indexes to delete, click **Manage index**, and then select **Delete index** from the INDEX OPTIONS drop-down list.

- Add a lifecycle policy

**Note:**

Before you add a lifecycle policy to an index, ensure that you have created an index lifecycle policy. For more information about how to create an index lifecycle policy, visit [Creating an index lifecycle policy](#).

- a. In the right-side index list, select the index that you want to modify, click **Manage index**, and then select **Add lifecycle policy** from the INDEX OPTIONS drop-down list.
- b. In the dialog box that appears, select a lifecycle policy and click **Add policy**.

8.2 Kafka Manager

8.2.1 What is Kafka Manager?

This topic describes features of Kafka Manager.

Kafka Manager is a web-based management system for Kafka. You can use Kafka Manager to manage Kafka clusters that consist of the logs from base modules. You can use Kafka Manager to perform visualized O&M operations on Kafka clusters of Log Service. For example, you can manage topics, brokers, and consumers in Kafka clusters.

8.2.2 Log on to Kafka Manager


This topic describes how to log on to Kafka Manager.

Prerequisites

- ASO access address in the format of `http://region-id.aso.intranet-domain-id.com`.
- Google Chrome browser (recommended).

Procedure

1. Open the browser.
2. Enter the ASO access address `http://region-id.aso.intranet-domain-id.com` in the address bar and then press Enter.

**Note:**

You can select the language from the drop-down list in the upper-right corner to change the language of ASO.

3. Enter the correct username and password.

**Note:**

Obtain the username and password used to log on to ASO from the deployment personnel or the administrator.

- The system has three default users:
 - Security officer: manages other users or roles.
 - Auditor officer: views audit logs.
 - System administrator: used for other functions except those of the security officer and auditor officer.
- You must modify the password of your username as instructed when you log on to ASO for the first time. To improve security, the password must be 10-20 characters long and can contain English uppercase/lowercase letters (A-Z or a-z), numbers (0-9), and special characters, such as exclamation points (!), at signs (@), number signs (#), dollar signs (\$), and percent signs (%), which meets the minimum complexity requirements.

4. Click **Log On** to log on to ASO.

5. In the left-side navigation pane, click **Products**.

6. On the **Product List** page, click **Platform Log Management** in the **Apsara Stack > Basic O&M** section.

8.2.3 Quick start


8.2.3.1 Create a Kafka cluster

If you use Kafka Manager for the first time, you must create a Kafka cluster.

Context

Procedure


1. In the top navigation bar of the Kafka Manager homepage, select **Add Cluster** from the **Cluster** drop-down list.



2. On the **Add Cluster** page, configure cluster parameters.

Parameter	Description
Cluster Name	Required. The name of the cluster to be created. After a cluster is created, its name cannot be changed.
Cluster Zookeeper Hosts	Required. The connection string of a ZooKeeper node in the cluster. Format: ip:port.
Kafka Version	The version of Apache Kafka. We recommend that you select the latest version.
Enable JMX Polling	We recommend that you select this option. Java Management Extensions (JMX) is a Java technology that supplies tools for monitoring and managing system objects, such as clearing cache and reloading the configuration file.
JMX Auth Username	The username for JMX authorization.

Parameter	Description
JMX Auth Password	The password for JMX authorization.
JMX with SSL	You can select this option to enable JMX over SSL.
Enable Logkafka	You can select this option to enable Logkafka. Logkafka sends log file content to Kafka line by line.
Poll consumer information	You can select this option to view consumer information in a Kafka cluster on the Consumers page. We recommend that you do not select this option if the number of the consumers is large.
Filter out inactive consumers	You can select this option to filter out inactive consumers.
Enable Active OffsetCache	You can select this option to enable active offset cache.
Display Broker and Topic Size	You can select this option to view the numbers of brokers and topics in the cluster.
brokerViewUpdatePeriodSeconds	The update period for broker views. Unit: seconds.
clusterManagerThreadPoolSize	The size of the thread pool for the cluster manager.
clusterManagerThreadPoolQueueSize	The size of the thread pool queue for the cluster manager.
kafkaCommandThreadPoolSize	The size of the thread pool for Kafka commands.
kafkaCommandThreadPoolQueueSize	The size of the thread pool queue for Kafka commands.
logkafkaCommandThreadPoolSize	The size of the thread pool for Logkafka commands.
logkafkaCommandThreadPoolQueueSize	The size of the thread pool queue for Logkafka commands.
logkafkaUpdatePeriodSeconds	The update period for Logkafka. Unit: seconds.
partitionOffsetCacheTimeoutSeconds	The timeout period of the partition offset cache. Unit: seconds.
brokerViewThreadPoolSize	The size of the thread pool for broker views.
brokerViewThreadPoolQueueSize	The size of the thread pool queue for broker views.
offsetCacheThreadPoolSize	The size of the thread pool for the offset cache.
offsetCacheThreadPoolQueueSize	The size of the thread pool queue for the offset cache.
kafkaAdminClientThreadPoolSize	The size of the thread pool for the Kafka administrator client.
kafkaAdminClientThreadPoolQueueSize	The size of the thread pool queue for the Kafka administrator client.

Parameter	Description
kafkaManagedOffsetMetadataCheckMillis	The check interval for the offset metadata.
kafkaManagedOffsetGroupCacheSize	The size of the offset group cache.
kafkaManagedOffsetGroupExpirationDays	The expiration period of the offset group.
Security Protocol	The security protocol.
SASL Mechanism (only applies to SASL based security)	The simple authentication and security layer (SASL) mechanism that only applies to SASL-based security.
SASL JAAS Config (only applies to SASL based security)	<p>The SASL-based Java Authentication and Authorization Service (JAAS) configurations, including the username and password.</p> <p>Example:</p> <pre>org.apache.kafka.common.security.plain.PlainLoginModule required username=username password=password;</pre> <div>  <p>Note:</p> <p>To mask sensitive information, developers configure this parameter within Apsara Stack Agility SE. You do not need to configure this parameter when creating a Kafka cluster.</p> </div>

3. Click **Save**.

Result

After a Kafka cluster is created, you can view the Kafka cluster in the cluster list of the Kafka Manager homepage.

What's next

To modify the configuration information of a Kafka cluster, perform the following steps: Go to the cluster list of the Kafka Manager homepage. Find the target cluster and click **Modify** in the **Operations** column.

8.2.3.2 View topics in a Kafka cluster


You can view the topics in a created Kafka cluster.

Prerequisites

A Kafka cluster is created. For more information about how to create a Kafka cluster, see [Create a Kafka cluster](#).

Procedure

1. In the cluster list of the Kafka Manager homepage, find the target cluster and click the cluster name.
2. In the top navigation bar, choose **Topic > List**.



3. In the **Topics** section, view the number of topics in the cluster, the number of messages in each topic, the rate at which messages are generated by each topic, and the number of Kafka nodes in which messages are stored.
4. Click a topic name to view its details.

8.2.3.3 View consumers in a Kafka cluster

If you select **Poll consumer information** when creating a cluster, you can view the topics that each consumer consumes on the cluster details page.

Context


Kafka consumers read and consume messages from Kafka servers. Kafka consumers are also known as message subscribers or message consumers.

Procedure

1. In the cluster list of the Kafka Manager homepage, find the target cluster.
2. Click the cluster name.

The cluster details page appears.

3. In the top navigation bar, click **Consumers**.



4. View all consumers in the cluster and their types.

5. Click a consumer and view the topics consumed by the consumer.

8.2.3.4 View brokers in a Kafka cluster

A broker is an independent Kafka server that runs in a Kafka Cluster. After a Kafka cluster is created, you can view the brokers in the Kafka cluster.


Procedure

1. In the cluster list of the Kafka Manager homepage, find the target cluster.

2. Click the cluster name.

The cluster details page appears.

3. In the top navigation bar, click **Brokers**.



Id	Host	Port	JMX Port	Bytes In
20	[REDACTED]	PLAINTEXT:9092	9999	
21	[REDACTED]	PLAINTEXT:9092	9999	
22	[REDACTED]	PLAINTEXT:9092	9999	

4. View information of brokers in a Kafka cluster, such as IDs, hosts, and ports.
5. Click a broker ID, and view details about the broker.

8.2.4 Kafka clusters

You can view, modify, disable, enable, and delete a Kafka cluster.

8.2.4.1 View a Kafka cluster

You can view topics and brokers in a Kafka cluster based on your requirements.

Procedure

1. In the cluster list of the Kafka Manager homepage, find the target cluster.
2. Click the cluster name.
The cluster details page appears.
3. In the **Cluster Summary** section, view the numbers of topics and brokers in the cluster.
4. Click the number following **Topics** or **Brokers** to view the information of all topics or brokers.

8.2.4.2 Disable or enable a Kafka cluster

This topic describes how to disable or enable a Kafka cluster based on your requirements.

Disable a Kafka cluster

After you create a Kafka cluster, the cluster is enabled by default. You can disable the Kafka cluster if you do not need to use it.

1. In the cluster list of the Kafka Manager homepage, find the target cluster.
2. Click **Disable** in the **Operations** column.

Enable a Kafka cluster

If you want to use a disabled cluster, enable it first.

1. In the cluster list of the Kafka Manager homepage, find the target cluster.
2. Click **Enable** in the **Operations** column.

8.2.4.3 Delete a Kafka cluster

This topic describes how to delete a Kafka cluster that you no longer use.

Prerequisites

The Kafka cluster is disabled. For more information about how to disable a Kafka cluster, see [Disable a Kafka cluster](#).

Procedure

1. In the cluster list of the Kafka Manager homepage, find the cluster you want to delete.
2. Click **Delete** in the **Operations** column.

8.2.5 Topics

A Kafka topic is a unique string associated with a message type. Messages in Kafka are classified by topic. A topic is divided into one or more partitions distributed across one or more brokers.

8.2.5.1 Create a Kafka topic

This topic describes how to create a Kafka topic.

Context




Note:

In Apsara Stack Agility SE, topic information is generated when Log Service is used. This function is not common in O&M scenarios and is for reference only.

Procedure

1. In the cluster list of the Kafka Manager homepage, find the cluster for which you want to create a topic, and click the cluster name.
2. In the top navigation bar, select **Create** from the **Topic** drop-down list.



3. On the **Create Topic** page, configure the topic parameters.

Parameter	Description
Topic	The name of the topic.
Partitions	<p>The number of partitions within the topic. The value must be an integer greater than 1.</p> <p>An appropriate partitioning strategy leads to higher throughput.</p>
Replication Factor	The number of replicas. Replicas ensures the high availability of Kafka clusters.

4. Click **Create**.

8.2.5.2 Generate partition assignments

This topic describes how to generate partition assignments for one or more topics. You can move multiple partitions at a time to reassign partitions. For example, you can reassign partitions to specified brokers when the number of brokers increases in a cluster or the number of partitions increases in a topic.

Context

Each topic has one or more partitions.

**Note:**

In Apsara Stack Agility SE, topic information is generated when Log Service is used. This function is not common in O&M scenarios and is for reference only.

Reassign partitions for a single topic

1. In the cluster list of the Kafka Manager homepage, find the cluster to which the target topic belongs, and click the cluster name.
2. In the top navigation bar, select **List** from the **Topic** drop-down list.
3. In the **Topics** section, find the topic for which you want to reassign partitions and click its name.
4. In the **Operations** section, click **Generate Partition Assignments**.
5. On the **Confirm Assignment** page, select a broker.

Confirm Assignment

Choose brokers to reassign topic __consumer_offsets to:

Brokers	Replication
<div> <div>Select All</div> <div>Select None</div> </div> <div> <input checked="" type="checkbox"/> 20 - <input checked="" type="checkbox"/> 21 - <input checked="" type="checkbox"/> 22 - </div>	<div>Replication factor (optional)</div> <div></div>
<div> <div>Cancel</div> <div>Generate Partition Assignments</div> </div>	

6. Click **Generate Partition Assignments**.

Reassign partitions for multiple topics at a time

1. In the cluster list of the Kafka Manager homepage, find the cluster to which the target topic belongs, and click the cluster name.
2. In the top navigation bar, select **List** from the **Topic** drop-down list.
3. In the **Operations** section, click **Generate Partition Assignments**.
4. On the **Confirm Assignments** page, select the topics for which you want to reassign partitions from the topic list and corresponding brokers from the broker list.
5. Click **Generate Partition Assignments**.

8.2.5.3 Add partitions

You can add partitions for one or more topics.

Context

**Note:**

In Apsara Stack Agility SE, topic information is generated when Log Service is used. This function is not common in O&M scenarios and is for reference only.

Add partitions for a single topic

1. In the cluster list of the Kafka Manager homepage, find the cluster to which the target topic belongs, and click the cluster name.
2. In the top navigation bar, select **List** from the **Topic** drop-down list.
3. In the **Topics** section, find the topic to which you want to add partitions and click its name.

4. In the **Operations** section, click **Add Partitions**.

[←](#) **__consumer_offsets**

Topic Summary

Replication	3
Number of Partitions	50
Sum of partition offsets	0
Total number of Brokers	3

Operations

Delete Topic

Reassign Partitions

Generate Partition Assignments

Add Partitions

Update Config

Manual Partition Assignments

5. On the **Add Partitions** page, select the broker and modify the number of partitions.



Note:

The **Partitions** field specifies the total number of partitions. The new number of partitions must be greater than the original number.

Add Partitions

Add PartitionsBrokers

Topic
__consumer_offsets

Partitions
50

Select All
Select None

☒ 20 - 10.20.8.68
☒ 21 - 10.20.8.64
☒ 22 - 10.20.8.60

Add PartitionsCancel


6. Click Add Partitions.

Add partitions for multiple topics

You can add partitions for multiple topics at a time. The new number of partitions must be greater than the maximum number of partitions of a topic among all topics.

1. In the cluster list of the Kafka Manager homepage, find the cluster to which the target topic belongs, and click the cluster name.

2. In the top navigation bar, select **List** from the **Topic** drop-down list.
3. In the **Operations** section, click **Add Partitions**.



4. In the **Partitions** field on the **Add Partitions** page, enter the number of partitions and select the topics and brokers for which you want to add partitions.

**Note:**

The new number of partitions must be greater than the maximum number of partitions of a topic among all topics.

5. Click **Add Partitions**.

8.2.5.4 Run partition assignments

This topic describes how to run partition assignments.

Procedure

1. In the cluster list of the Kafka Manager homepage, find the cluster to which the target topic belongs, and click the cluster name.
2. In the top navigation bar, select **List** from the **Topic** drop-down list.
3. In the **Operations** section, click **Run Partition Assignments**.

4. On the **Run Assignments** page, select the topic for which you want to reassign partitions. Click **Run Partition Assignments**.

Run Assignments

Choose topics to reassign:

Topics

Select All

Select None

☒ ali-audit-project_audit_log

☒ ali-rds-perf_rds_perf

☒ kafka_elk-python_service_test

☒ tjm-yundun-security-auditlog_auditlog

☒ ali-pop-log_pop_system_log

☒ rds-project_prd_rds_sql

☒ ali-pop-log_pop_rpc_trace_log

☒ server_test_log_store_name

☒ kafka_python_service_test

☒ rds-project_bifrost-rds

☒ __consumer_offsets

Run Partition Assignments

8.2.5.5 Reassign partitions

This topic describes how to reassign partitions. To balance cluster loads, you can reassign partitions to elect a new leader for assigned replicas.

Procedure

1. In the cluster list of the Kafka Manager homepage, find the cluster to which the target topic belongs, and click the cluster name.
2. In the top navigation bar, select **List** from the **Topic** drop-down list.
3. In the **Topics** section, find the target topic and click its name.

4. In the **Operations** section, click **Reassign Partitions**.

8.2.5.6 Update configurations for a topic

This topic describes how to update configurations for a Kafka topic.

Procedure

1. In the cluster list of the Kafka Manager homepage, find the cluster to which the target topic belongs, and click the cluster name.
2. In the top navigation bar, select **List** from the **Topic** drop-down list.
3. In the **Topics** section, find the target topic and click its name.
4. In the **Operations** section, click **Update Config**.
5. On the **Update Config** page, update the configurations for the topic.

Parameter	Description	Default value
Topic	The name of the topic.	N/A
cleanup.policy	The cleanup policy on old log segments. Valid values: <ul style="list-style-type: none"> • delete: deletes log segments. • compact: compresses log segments. 	delete
compression.type	The compression type specified for the topic. Valid values: <ul style="list-style-type: none"> • gzip • snappy • lz4 • uncompressed • producer: specifies the original compression encoder set by the producer. 	producer
delete.retention.ms	The maximum amount of time to retain compressed log data. Unit: milliseconds.	86400000, which is one day
file.delete.delay.ms	The time to wait before deleting a file from the file system. Unit: milliseconds.	60000, which is one minute

Parameter	Description	Default value
flush.messages	The number of messages written to a log partition before you force an fsync on the log. We recommend that you do not modify the default value.	9223372036854775807
flush.ms	The time interval at which you force an fsync of data written to the log. We recommend that you do not modify the default value.	9223372036854775807
follower.replication.throttled.replicas	The list of replicas for which log replication must be throttled on the follower side.	N/A
index.interval.bytes	The frequency at which Kafka adds an index entry to its offset index. We recommend that you do not modify the default value.	4096
leader.replication.throttled.replicas	The list of replicas for which log replication must be throttled on the leader side.	N/A
max.message.bytes	The largest record batch size allowed by Kafka.	1000012, which is about 1 MB

Parameter	Description	Default value
message.downconversion.enabled	Specifies whether down-conversion of message formats is enabled to satisfy the requests from consumers. When this parameter is set to false, the broker will not perform down-conversion for consumers that are configured to receive older message format. The broker returns the UNSUPPORTED_VERSION error to these the requests from consumers. This configuration does not apply if the message conversion format is required to enable replication to followers.	true
message.format.version	Specifies the message format version that the broker uses to append messages to the log. The value must be a valid API version.	N/A
message.timestamp.difference.maximum	The maximum difference allowed between the timestamp when the broker receives a message and the timestamp specified in the message. When message.timestamp.type is set to CreateTime, a message will be rejected if the difference in timestamp exceeds this threshold. When message.timestamp.type is set to LogAppendTime, this parameter is ignored.	9223372036854775807

Parameter	Description	Default value
message.timestamp.type	The timestamp type in the message. The value can be CreateTime or LogAppendTime.	CreateTime
min.cleanable.dirty.ratio	The frequency at which the log compactor will attempt to clean the log.	0.5
min.compaction.lag.ms	The minimum amount of time a message will remain uncompressed in the log . This parameter is only applicable to logs that are being compressed.	0
min.insync.replicas	The minimum number of in-sync replicas that acknowledge a write operation to be considered successful.	1
preallocate	Specifies whether to preallocate a file on the disk when you create a new log segment.	false
retention.bytes	The maximum size of a partition. If the maximum size is reached, you can discard old log segments to free up space by using the "delete" retention policy.	-1
retention.ms	The maximum amount of time to retain a log. If the maximum time is reached , you can discard old log segments by using the "delete" retention policy. Unit: milliseconds.	604800000, which is seven days
segment.bytes	The segment file size for the log.	1073741824, which is 1 GB

Parameter	Description	Default value
segment.index.bytes	The size of the index that maps offsets to file positions.	10485760, which is 10 MB
segment.jitter.ms	The maximum random jitter subtracted from the scheduled segment roll time to avoid thundering herds of segment rolling.	0
segment.ms	The period of time after which Kafka will force the log to roll even if the segment file is not full. This ensures that retention can delete or compress old data . Unit: milliseconds.	604800000, which is seven days
unclean.leader.election.enable	Specifies whether an out-of-sync replica is elected as the leader when there is no live in-sync replica (ISR).	false

6. Click **Update Config**.

8.2.5.7 Manually assign partitions

The system allows you to manually assign brokers for replicas in each partition. You can assign partitions if a broker or a broker leader is skewed.

Procedure

1. In the cluster list of the Kafka Manager homepage, find the cluster to which the target topic belongs, and click the cluster name.
2. In the top navigation bar, select **List** from the **Topic** drop-down list.
3. In the **Topics** section, find the target topic and click its name.
4. In the **Operations** section, click **Manual Partition Assignments**.

5. On the **Manual Partition Assignments** page, reassign brokers for replicas in each partition.

Manual Partition Assignments

Save Partition Assignment

Type to filter topics

ali-audit-project_audit_log

Partition 0
Replica 0: Broker 21
Replica 1: Broker 22

Partition 1
Replica 0: Broker 22
Replica 1: Broker 20

Partition 3
Replica 0: Broker 21
Replica 1: Broker 20

Partition 5
Replica 0: Broker 20
Replica 1: Broker 22

Partition 2
Replica 0: Broker 20
Replica 1: Broker 21

Partition 4
Replica 0: Broker 22
Replica 1: Broker 21

6. Click **Save Partition Assignments**.

8.2.5.8 Configure automatic partition assignment

The system automatically assigns brokers for replicas in each partition.

Procedure

1. In the cluster list of the Kafka Manager homepage, find the cluster to which the target topic belongs, and click the cluster name.
2. In the top navigation bar, select **List** from the **Topic** drop-down list.
3. In the **Topics** section, find the topic and click its name.
4. In the **Operations** section, click **Create Partition Assignments**.

8.2.5.9 Delete a topic

This topic describes how to delete a topic that you no longer need based on your requirements.

Procedure

1. In the cluster list of the Kafka Manager homepage, find the cluster to which the target topic belongs, and click the cluster name.
2. In the top navigation bar, select **List** from the **Topic** drop-down list.
3. In the **Topics** section, find the topic you want to delete and click its name.
4. In the **Operations** section, click **Delete Topic**.
5. On the confirmation page, click **Delete Topic**.

9 PaaS operations and maintenance

9.1 PaaS console

9.1.1 PaaS console overview

The PaaS console is designed based on the platform and products. The console is mainly used to view, manage, and upgrade the products deployed in the PaaS console. The PaaS console also provides task management capabilities to support orchestration, O&M, and custom extension.

9.1.2 Log on to the PaaS console

This topic describes how to log on to the PaaS console.


Prerequisites

- The URL of the Apsara Stack Operations console is obtained. The URL of the Apsara Stack Operations console is in the following format: `http://region-id.aso.intranet-domain-id.com`.
- We recommend that you use the Google Chrome browser.

Procedure

1. Open your Chrome browser.

2. In the address bar, enter `http://region-id.aso.intranet-domain-id.com` and press Enter.

The image shows a dark-themed login interface. At the top, the text "Log On" is displayed in a large, white, sans-serif font. Below this, there are two input fields. The first field is preceded by a user icon and contains the placeholder text "Enter a user name". The second field is preceded by a lock icon and contains the placeholder text "Enter the password". At the bottom of the form is a prominent blue rectangular button with the white text "Log On".

Note:

You can select a language from the drop-down list in the upper-right corner.

3. Enter your username and password.



Note:

You can obtain the username and password used to log on to the Apsara Stack Operations console from the administrator or deployment personnel.

- By default, the following user roles are available:
 - Security administrator: the user who has the permissions to manage other users or roles.
 - Auditor: the user who has the permissions to view audit logs.
 - Sysadmin: the user who has more permissions than a security administrator and an auditor.
- The first time you log on to the Apsara Stack Operations console, you must change the password as prompted. To ensure security, your password must meet the complexity requirements. The password must be 10 to 20 characters in length. It must contain the following character type: uppercase letters, lowercase letters, digits, and special characters. Special characters include ! @ # \$ %

4. Click **Log On** to access the **Apsara Stack Operations console**.

5. In the left-side navigation pane, click **Products**.
6. In the **Basic O&M** section of the **Products** page, click **PaaS Console**.

9.1.3 Platform overview

On the **Overview** page, view status statistics of platform products and clusters.

Procedure

1. Log on to the PaaS console.

The **Overview** page appears by default.

2. On the **Overview** page, view status statistics of platform products and clusters.

The page contains two sections:

- Platform Product Overview: displays status statistics of products deployed in the PaaS console. Click the **Total** value to go to the **Product Center > Products** page.
- Cluster Overview: displays status statistics of nodes and pods in clusters. Click a status value of **Node Status** to go to the **Clusters > Nodes** page. Click the **Not Ready** value of **Pod Status** to view error messages of abnormal pods.

Platform Product Overview

Total

6

Ready

5

Not Ready

1

Cluster Overview

Clusters: tianji-paas-a-09f7

API Server Endpoint: https://[redacted].com:6443

Node Status

Ready

11

Not Ready

0

Pod Status

Total

97

Running

96

Successful

1

Not Ready

0

9.1.4 Clusters

9.1.4.1 View the cluster list

On the **Clusters** page, you can view the status and kubeconfig connection information of clusters managed by PaaS.

Procedure

1. Log on to the PaaS console.

2. In the left-side navigation pane, choose **Clusters > Clusters**.

3. On the **Clusters** page, view all clusters managed by PaaS.

Clusters			
Name	Status	Registration Time	Actions
kubernetes	Available	Apr 6, 2020, 09:19:25	View

4. Find a cluster and click **View** in the **Actions** column to view the kubeconfig connection information of the cluster.

9.1.4.2 Node management

You can add node tags or taints for clusters to manage scheduling policies.

9.1.4.2.1 Add a tag

You can add tags to nodes based on your business needs for subsequent cluster scheduling, configuration, and behavior customization.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Clusters > Nodes**.
3. Optional: In the upper-left corner of the Nodes page, select the target cluster from the drop-down list.
4. Select one or more nodes to which you want to add a tag. Click **Add Label** in the lower-left corner.

5. Perform the following operations:

- Add a built-in tag

In the **Add Label to Node** dialog box that appears, click a tag in the Built-in Labels field. The tag name is automatically filled into the Key field. Set **Value** and then click **OK**.

The following table describes the parameters.

Parameter	Description
Built-in Labels	Existing tags in the system. Valid values: <ul style="list-style-type: none"> - Hypervisor failure-domain: During virtualization output, virtual machines are distributed on different physical machines. This tag can be used to distribute pods to different physical machines. - Zone failure-domain: distributes Kubernetes nodes to different zones. - Region failure-domain: distributes Kubernetes nodes to different regions.
Key	After you click a tag in the Built-in Labels field, the tag name is automatically filled into the Key field. You can also set Key directly to specify a custom tag.
Value	The custom tag value.

The screenshot shows the 'Add Label to Node' dialog box. It features a title bar with the text 'Add Label to Node' and a close button (X). Below the title bar, there is a section labeled 'Built-in Labels' which contains three buttons: 'Hypervisor failure-domain', 'Zone failure-domain', and 'Region failure-domain'. Below these buttons are two text input fields: 'Key' and 'Value'. At the bottom right of the dialog, there are two buttons: 'OK' and 'Cancel'.

- Add a custom tag

In the **Add Label to Node** dialog box that appears, set Key and Value, and then click **OK**.

9.1.4.2.2 Add a taint

You can add taints to nodes based on your business needs for subsequent pod scheduling.

Procedure


1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Clusters > Nodes**.
3. Optional: In the upper-left corner of the Nodes page, select the target cluster from the drop-down list.
4. Select one or more nodes to which you want to add a taint. Click **Add Taint** in the lower-left corner.
5. Perform the following operations:
 - Add a built-in taint

In the **Add Taint** dialog box that appears, click a taint in the Built-in Taints field. The taint name is automatically filled into the Key field. Specify **Value** and **Effect**, and then click **OK**.

The following table describes the parameters.

Parameter	Description
Built-in Taints	Existing taints in the system.
Key	After you click a taint in the Built-in Taints field, the taint name is automatically filled into the Key field. You can also set Key directly to specify a custom taint.
Value	The custom taint value.

Parameter	Description
Effect	<p>The effects of the taint. Valid values:</p> <ul style="list-style-type: none"> - PreferNoSchedule: indicates that pods will not schedule the node if possible. - NoSchedule: indicates that pods will not be allowed to schedule the node. - NoExecute: indicates that pods will not be allowed to schedule the node and that pods that are running on the node will be evicted.



The 'Add Taint' dialog box is shown. It has a title bar with 'Add Taint' and a close button. Below the title bar, there is a section for 'Built-in Taints' with a button labeled 'Default NoSchedule'. Underneath, there are two input fields: 'Key' and 'Value'. Below these fields, there is a section for 'Effect' with three radio buttons: 'PreferNoSchedule', 'NoSchedule' (which is selected), and 'NoExecute'. At the bottom right, there are two buttons: 'OK' and 'Cancel'.

- Create a custom taint

In the **Add Taint** dialog box that appears, specify **Key**, **Value**, and **Effect**, and then click **OK**.

9.1.4.2.3 Query nodes by tag

You can filter nodes by tag to quickly find nodes that have a specified tag.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Clusters > Nodes**.


3. In the upper-right corner of the page, enter a tag name or **key=value** in the search box and then click the search icon.

tianji-paas-a-ab21		Search by key=value	
Status	IP	Node Information	
<input type="checkbox"/>	● Ready	<div>Name</div> <div>a56b08103.cloud.b09.amte...</div> <div>Role</div> <div>master,minio-0,prometheu...</div>	<div>Labels</div> <div>aliyuncs.l:true aliyuncs.l:true apsarastac:1 apsarastac:... apsarastac:t... seed.local:tr...</div> <div>Taints</div> <div>apsarastac...</div>
<input type="checkbox"/>	● Ready	<div>Name</div> <div>a56b08107.cloud.b09.amte...</div> <div>Role</div> <div>worker</div>	<div>Labels</div> <div>apsarastac:10 apsarastac...</div> <div>Taints</div> <div>apsarastac...</div>
<input type="checkbox"/>	● Ready	<div>Name</div> <div>a56b08108.cloud.b09.amte...</div> <div>Role</div> <div>master,minio-1,prometheu...</div>	<div>Labels</div> <div>aliyuncs.l:true aliyuncs.l:true apsarastac:1 apsarastac:... apsarastac:t... seed.local:tr...</div> <div>Taints</div> <div>apsarastac...</div>

9.1.4.2.4 Delete a tag

You can delete built-in or custom tags from nodes. Kubernetes-defined tags of nodes cannot be deleted.


Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Clusters > Nodes**.
3. Optional: In the upper-left corner of the Nodes page, select the target cluster from the drop-down list.
4. Find the target node. Find the target tag in the **Labels** row and click the  icon.



Note:

You can select the **Hide Kubernetes-defined Labels** check box to hide Kubernetes-defined tags, so that you can quickly find the target tag.


Nodes <input checked="" type="checkbox"/> Hide Kubernetes-defined Labels			
tianji-paas-a-ab21			
	Status	IP	Node Information
<input type="checkbox"/>	● Ready		Name a56b08103.cloud.b09.amte... Role master,minio-0,prometheu...
			Labels aliyuncs.l:true  aliyuncs.l:true apsarastac:1 apsarastac:... apsarastac:t... seed.local:tr...
			Taints apsarastac...
<input type="checkbox"/>	● Ready		Name a56b08107.cloud.b09.amte... Role worker
			Labels apsarastac:10 apsarastac:...
			Taints apsarastac...
<input type="checkbox"/>	● Ready		Name a56b08108.cloud.b09.amte... Role master,minio-1,prometheu...
			Labels aliyuncs.l:true aliyuncs.l:true apsarastac:1 apsarastac:... apsarastac:t... seed.local:tr...
			Taints apsarastac...


5. In the message that appears, click **OK**.

9.1.4.2.5 Delete a taint

You can delete taints from nodes based on business needs.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Clusters > Nodes**.
3. Optional: In the upper-left corner of the Nodes page, select the target cluster from the drop-down list.
4. Find the target node. Find the target taint in the **Taints** row and click the  icon.

Nodes <input checked="" type="checkbox"/> Hide Kubernetes-defined Labels			
tianji-paas-a-ab21			
	Status	IP	Node Information
<input type="checkbox"/>	● Ready		Name a56b08103.cloud.b09.amte... Role master,minio-0,prometheu...
			Labels aliyuncs.l:true aliyuncs.l:true apsarastac:1 apsarastac:... apsarastac:t... seed.local:tr...
			Taints apsarastac... 
<input type="checkbox"/>	● Ready		Name a56b08107.cloud.b09.amte... Role worker
			Labels apsarastac:10 apsarastac:...
			Taints apsarastac...

5. In the message that appears, click **OK**.

9.1.5 Product center

9.1.5.1 Product list

The product list displays the information about all products deployed in the PaaS console, including their names and versions. In the product list, you can perform O&M operations and view product resources or register variables. You can also remove products that are no longer needed.

9.1.5.1.1 View product details

You can view the details of products deployed in the PaaS console, including their names, versions, and components.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Product Center > Products**.
3. In the product list, find the target product and click **Details** in the **Actions** column.

Products Refresh					
Deployment Status	Status	Product Name	Product version / Branch	Build version	Actions
Upgrade Succeeded	• Ready	ark agility-standard		51gpr4o6mo1fat4intqosjnfb.109172	Details
Install Succeeded	• Ready	cluster-init standard		51gpr4o6mo1fat4intqosjnfb.109172	Details
Install Succeeded	• Ready	drds standard		3k3jj0kn82rjt63arvaf8emvgj.123456	Details
Upgrade Succeeded	• Not Ready	drds-autotest standard		fb349068-14ee-4968-b37e-a957dd80a786.123456	Details

4. On the **Overview** page, view the name, version information, and components of the product.


ark - agility-standard Refresh						
<div> <div>100%</div> <div>Product Name: ark - agility-standard Components: 5</div> <div>Product Version: 51gpr4o6mo1fat4intqosjnfb.109172</div> </div>						
Product Components Refresh						
Deployment Status	Status	Cluster	Namespace	Name	Version	Actions
Install Succeeded	• Ready	tianji-paas-a-09f7	ark-system	ark-diagnose	1.1.0-6f80bc8	Details Deployment Progress
Install Succeeded	• Ready	tianji-paas-a-09f7	default	init-ark-apigateway	0.1.0-6ca7870	Details Deployment Progress
Upgrade Succeeded	• Ready	tianji-paas-a-09f7	ark-system	bridge-console	1.6.1-4677890	Details Deployment Progress
Install Succeeded	• Ready	tianji-paas-a-09f7	kong	kong	0.18.0-3de4227	Details Deployment Progress
Install Succeeded	• Ready	tianji-paas-a-09f7	ark-system	ark-gatekeeper	0.1.0-ba241e6	Details Deployment Progress

9.1.5.1.2 View component information

You can view the component details in the Product Components section of the **Overview** page of a product.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Product Center > Products**.
3. In the product list, find the target product and click **Details** in the **Actions** column.
4. In the Product Components section of the **Overview** page, view deployment information of components, such as their clusters, namespace, names, deployment states, and versions.
5. Find a component and click **Details** in the **Actions** column to view details of the component.
6. The **Component Details** page contains the following tabs: StatefulSets, Deployments, DaemonSets, Jobs, Services, and Persistence Volume Claims.



Component: middleware.zookeeper.zk						
Lists						
StatefulSets	Deployments	DaemonSets	Jobs	Services	Persistent Volume Claims	
Name	Namespace	Desired Count	Current Count	Ready Count	Creation Time	Actions
zk-middleware	default	3	3	3	Mar 31, 2020, 11:38:55	Start Terminal


9.1.5.1.3 View the deployment progress of product components

You can view the deployment progress of product components.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Product Center > Products**.
3. In the product list, find the target product and click **Details** in the **Actions** column.

4. In the Product Components section of the **Overview** page, find the target component and click **Deployment Progress** in the **Actions** column.



zookeeper - standard

100%

Product Name: zookeeper - standard Components: 1

Product Version: 3k3jj0kn82rjt63arvaf8emvgj.123456

Product Components Refresh


Deployment Status	Status	Cluster	Namespace	Name	Version	Actions
Install Succeeded	Ready	tianji-paas-a-09f7	default	middleware.zookeeper.zk	0.1.0-4244bd6	Details Deployment Progress

5. On the **Product Component Deployment Progress** page, click deployment nodes in sequence to view the deployment progress and logs of the current component.



Note:

You can click **LOGS** in the lower-left corner of the Summary tab to view deployment logs.



Product Component Deployment Progress

inst-middleware-zook...

AnalyseContext

GenerateResources

CheckDependency

IMAGE

cn:...

inc.com/alibaba_apsara_paas/ark-workflow:v1.0.4-reserve-ip

COMMAND

python

ARGS

/ark-argo-workflow/scripts/context_analysis.py
 {{workflow.parameters.contextName}} {{workflow.parameters.contextNS}}
 {{workflow.parameters.option}} {{workflow.parameters.cmdbNS}}

LOGS

9.1.5.1.4 Log on to a web terminal

The **StatefulSets** and **Deployments** tabs of the **Component Details** page list available terminals. Browser-based terminals are mainly used for O&M management and troubleshooting.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Product Center**.
3. In the product list, find the target product and click **Details** in the **Actions** column.

4. In the Product Components section of the **Overview** page, find the target component and click **Details** in the **Actions** column.
5. On the **Component Details** page, click the **StatefulSets** or **Deployments** tab.
6. Find the target component. Click **Start Terminal** in the **Actions** column.

Available containers that are based on the number of replicas are displayed in the pane.

Lists						
StatefulSets	Deployments	DaemonSets	Jobs	Services	Persistent Volume Claims	
Name	Namespace	Desired Count	Current Count	Ready Count	Creation Time	Actions
zk-middleware	default	3	3	3	Mar 31, 2020, 13:38:59	Start Terminal

7. Select the target container and then click **OK** to start the terminal process.

9.1.5.1.5 Perform O&M actions

The **O&M Actions** page displays the O&M actions available to a product. You can also perform O&M actions on this page.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Product Center > Products**.
3. In the product list, find the target product and click **Details** in the **Actions** column.
4. In the left-side navigation pane, click **O&M Actions**.
5. Perform O&M actions available to the product.




9.1.5.1.6 View a resource report

The **Resource Report** page displays information of all resources that a product has requested from the PaaS console. The resource type can be cni (ip), db, vip, dns, and accesskey.


Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Product Center > Products**.
3. In the product list, find the target product and click **Details** in the **Actions** column.

4. In the left-side navigation pane, click **Resource Report**.

Resource Report			
Resource Owner 	Type 	Key	Value
middleware.zookeeper.zk	cni	cni.zookeeper.ip_list	10.24. 

5. View information of resources.

By default, all resources are displayed. You can click the up and down arrows next to **Resource Owner** to sort resources. You can also click the  icon next to **Type** to filter resources.






Parameter	Description
Resource Owner	The name of the component to which the resource belongs.
Type	The type of the resource.
Key	The attribute name of the resource.
Value	The attribute value of the resource.

9.1.5.1.7 View service registration variables


The Service Registration Variables page displays the values of all service registration variables. You can view the service registration variables of a product based on business needs. The service registration variables report for a product lists the variables that the product can deliver to other products or components.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Product Center > Products**.
3. In the product list, find the target product and click **Details** in the **Actions** column.
4. In the left-side navigation pane, click **Service Registration Variables**.

Service Registration Variables		
Resource Owner  	Key	Value
edas.edasservice.cai-fs	edas_cai_fs_db_host	db.a 
edas.edasservice.cai-fs	edas_cai_fs_db_name	efs
edas.edasservice.cai-fs	edas_cai_fs_db_password	
edas.edasservice.cai-fs	edas_cai_fs_db_port	3306
edas.edasservice.cai-fs	edas_cai_fs_db_user	efs
edas.edasservice.cai-fs	edas_cai_fs_domain	fileserve 

5. View information of service registration variables.

By default, all service registration variables are displayed. You can click the up and down arrows next to **Resource Owner** to sort service registration variables. You can also click the  icon next to **Resource Owner** to filter service registration variables.

The following table describes the parameters for the service registration variables list.

Parameter	Description
Resource Owner	The name of the component to which the resource belongs.
Key	The variable name that is registered on the CMDB and can be used by this product or other product components .
Value	The variable value that is registered on the CMDB.

9.1.5.2 Deployment and upgrade

You can perform batch upgrade and incremental deployment. You can deploy a product by product feature. If the product supports custom configuration, the system automatically enters the custom configuration page.

Prerequisites

Confirm that the deployment upgrade package has been imported to the PaaS console.

You can import the deployment package in the following way:

1. Upload the installation disk used for deployment to the bootstrap node in the on-site environment.
2. Log on to the bootstrap node over SSH.
3. Run the following command to import the deployment package and generate a deployment package list:

```
sh upgrade.sh {packages -path}.iso
```

Replace {packages -path}.iso with the actual storage path of the iso file on the installation disk.

Procedure

1. Log on to the PaaS console.

2. In the left-side navigation pane, choose **Product Center > Deploy&Upgrade**.

The **System Packages** page displays deployment packages that have been imported to the PaaS console.

3. Find the target deployment package in the **System Packages**.



Note:

If there are many deployment packages, you can enter the system ID in the search box to query a deployment package that meets the condition.

System Packages			
Filter by system ID			Q
System ID	Build Time	Import Time	Actions
fb349068-14ee-4968-b37e-a957dd80a786.123456	Mar 30, 2020, 22:27:13	Mar 30, 2020, 22:27:13	Deploy
3k3jj0kn82rjt63arvaf8emvgj.123456	Mar 30, 2020, 21:47:40	Mar 30, 2020, 21:47:40	Deploy
51gpr4o6mo1fat4intqosjnfbs.109172	Mar 29, 2020, 18:45:03	Mar 29, 2020, 18:45:03	Deploy

4. Click **Deploy** in the **Actions** column to start the deployment or upgrade process.
5. Optional: In the **Select Products** step, click the number in the **Components** column to view the components and versions for the current product.

Notice: Welcome to the Apsara Agility PaaS Operations console.

Select Products Customize Configurations Node Planning Preview

System ID: fb349068-14ee-4968-b37e-a957dd80a786.123456 ☒ Automatic Dependency Processing

<input type="checkbox"/>	Product & Feature	Description	Components
	drds-autotest - (apsara_paas/v3.2.0xR@821070eefa7f1de754e52f495035f4dd87a84482)		
<input type="checkbox"/>	standard	Default feature description	1

Selected Products: 0, Total Components: 0

Next

6. Select the required features and click **Next**.



Note:

The system can automatically parse dependencies between products. When the Automatic Dependency Processing check box is selected, the system will automatically check whether dependencies exist between deployed products and products to be deployed and then select dependent products. If you want to manually select the





products to be deployed, you can clear the **Automatic Dependency Processing** check box. If you select products that have been deployed, the system upgrades these products. If you select products that have not been deployed, the system performs incremental deployment to these products.

If the custom configuration feature is enabled for a selected product, the **Customize Configurations** page is displayed. Otherwise, the **Preview** page is displayed.

7. In the **Customize Configurations** step, configure the parameters as prompted and then click **Save**. Click **Next**.


8. In the **Preview** step, check the information of the products to be deployed.


Icons before **Product & Feature** indicate different states of products:

- : indicates that the product is newly deployed.
- : indicates that the product has been deployed and does not need to be updated.
- : indicates that the product is updated. You can click the  icon to check product differences.

Notice: Welcome to the Apsara Agility PaaS Operations console.

Select Products > Customize Configurations > Node Planning > Preview

 You will submit the deploy or upgrade operation. Confirm the information to be submitted carefully, including the System ID of the deployment package and the affected products. If the information is correct, click Submit to submit the information. If modification is...

	Product & Feature	Description	Deployment Model	Components
drds-autotest - (apsara_paas/v3.2.0xR@821070eefa7f1de754e52f495035f4dd87a84482)				
	standard	Default feature description	Hybrid	1

Reselect Previous Submit

9. Click **Submit** to start the deployment process.

After the deployment process is started, you can view the progress on the **Task Center > Task Instances** page.

9.1.6 Task center

The Task Center module provides general task management capabilities. You can view and run task templates, and view, suspend, resume, terminate, and delete tasks.

9.1.6.1 Task templates



The Task Templates page lists all task templates, both imported and preset.

9.1.6.1.1 View a task template

On the Task Templates page, you can view information of all task templates, such as the name, description, parameters, and workflow definition.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Task Center** > **Task Templates**.
3. Find the target task template. Click **View** in the **Actions** column.

Task Templates Refresh			
Name	Description	Creation Time	Actions
app-instance-workflow-cm		Mar 29, 2020, 18:44:10	View Run
cluster-init-workflow		Mar 29, 2020, 18:42:45	View Run

4. In the pane that appears, view the name, description, parameters, and workflow definition of the task template.

Notice: Welcome to the Apsara Ag

Task Templates

Name

app-instance-workflow-cm

cluster-init-workflow

View Task Template Definition

Parameter	Default Value
contextName ?	NotNull
contextNS ?	ark-system
option ?	NotNull
cmdbNS ?	ark-system

Task Workflow Definition

```

1  apiVersion: argoproj.io/v1alpha1
2  kind: Workflow
3  metadata:
4    annotations:
5      ark-system/description: "\u4EA7\u54C1\u90E8\u7F72\u3001\u5347\u7EA7\u54C1\u90E8\u7F72"
6      \u7EBF
7      ark-system/parameters-constraints: '[{"name": "contextName", "constraints": [{"required": "true"}]}, {"name": "contextNS", "constraints": [{"required": "true"}]}, {"name": "option", "constraints": [{"required": "true"}]}]'
8      "true"}]}, {"name": "contextNS", "constraints": [{"required": "true"}]}, {"name": "option", "constraints": [{"required": "true"}]}]'
9      "option", "constraints": [{"required": "true"}]}]'
10 generateName: app-instance-process-
11 spec:
12   affinity:
13     nodeAffinity:
14       preferredDuringSchedulingIgnoredDuringExecution:
15         - preference:

```

9.1.6.1.2 Run a task

You can run tasks on the Task Templates page.


Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Task Center** > **Task Templates**.
3. Find the target task template. Click **Run** in the **Actions** column.
4. In the pane that appears, set Task Instance Name and Action Parameters as needed.



Note:

If the task instance name is not specified, the system will automatically generate a task instance name. We recommend that you enter a recognizable name for easy query.



Notice: Welcome to the Apsara Ag

Task Templates

Name

app-instance-workflow-cm

cluster-init-workflow

Run Task Immediately

Task Template Name

app-instance-workflow-cm

Task Functionality

Task Instance Name

Action Parameters

Parameter	Value
contextName ?	NotNull
contextNS ?	ark-system
option ?	NotNull
cmdbNS ?	ark-system

OK Cancel

5. Click **OK**.

9.1.6.2 Task instances

The Task Instances page displays information of all tasks. On this page, you can view, suspend, resume, terminate, retry, and delete tasks.

9.1.6.2.1 View task details

After you run a task, you can view the progress, logs, and parameters of the task on the Task Instances page.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Task Center** > **Task Instances**.

3. In the task instance list, view the status of all tasks.

Valid values of the task status:

- **Succeeded**: indicates that the task has been executed.
- **Running**: indicates that the task is being executed.
- **Running (Suspended)**: indicates that the task is suspended.
- **Failed**: indicates the task has failed.
- **Failed (Terminated)**: indicates that the task is terminated.

4. Find the target task. Click **View** in the **Actions** column. Then you are redirected to the **Task Instance Details** page.

Task Instances Refresh				
Name	Status	Start Time	End Time	Actions
upg-drds-console-service-test-j99nr	Succeeded	Mar 30, 2020, 22:27:43	Mar 30, 2020, 22:28:28	View Delete
ark-fb349068-14ee-4968-b37e-a957dd80a786.123456	Succeeded	Mar 30, 2020, 22:27:13	Mar 30, 2020, 22:27:56	View Delete
inst-drds-console-drds-console-9k8mg	Succeeded	Mar 30, 2020, 21:48:11	Mar 30, 2020, 21:59:47	View Delete

5. On the Task Instance Details page, click task nodes in sequence to view the information and logs of the current task.



Note:

You can click **LOGS** in the lower-left corner of the Summary tab to view task logs.

9.1.6.2.2 Suspend a task

You can suspend a task which is in the **Running** state. Then the task status becomes Running (Suspended).

Prerequisites

Confirm that the task is in the **Running** state.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Task Center > Task Instances**.

3. In the task instance list, find a task which is in the **Running** state and you want to suspend. Click **Suspend** in the **Actions** column.

After a successful operation, the task **Status** turns from **Running** to **Running (Suspended)**.

9.1.6.2.3 Resume a task

After a task is suspended, the task is in the **Running (Suspended)** state. Then you can click **Resume** in the **Actions** column to resume the task.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Task Center > Task Instances**.
3. In the task instance list, find a task which is in the **Running (Suspended)** state and you want to resume. Click **Resume** in the **Actions** column.

After a successful operation, the task **Status** turns from **Running (Suspended)** to **Running**.

Task Instances				Refresh
Name	Status	Start Time	End Time	Actions
test	Running (Suspended)	Mar 31, 2020, 14:00:17		View Resume Stop Delete
upg-drds-console-service-test-j99nr	Succeeded	Mar 30, 2020, 22:27:43	Mar 30, 2020, 22:28:28	View Delete

9.1.6.2.4 Terminate a task

When a task is in the **Running (Suspended)** or **Running** state, you can click Stop to terminate the task.

Prerequisites

Confirm that the task is in the **Running (Suspended)** or **Running** state.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Task Center > Task Instances**.

3. In the task instance list, find a task which is in the **Running (Suspended)** or **Running** state. Click **Stop** in the **Actions** column.

For a task whose **Status** is **Running**, the system will immediately terminate the task and the task status becomes **Failed (Terminated)**. For a task whose **Status** is **Running (Suspended)**, the system will immediately terminate the task when the task status becomes Running again. Then the task status becomes **Failed (Terminated)**.

Task Instances					Refresh
Name	Status	Start Time	End Time	Actions	
test	Running (Suspended)	Mar 31, 2020, 14:00:17		View Resume Stop Delete	
upg-drds-console-service-test-j99nr	Succeeded	Mar 30, 2020, 22:27:43	Mar 30, 2020, 22:28:28	View Delete	

9.1.6.2.5 Retry a task

When a task is in the **Failed** or **Failed (Terminated)** state, you can click **Retry** to run the task again. When a task is retried, the task starts again from the failed or terminated task node.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Task Center > Task Instances**.

3. In the task instance list, find a task which is in the **Failed** or **Failed (Terminated)** state. Click **Retry** in the **Actions** column.

Notice: Welcome to the Apsara Agility PaaS Operations console.				
inst-drds-console-drds-logger-hpfbk	Succeeded	Mar 30, 2020, 21:48:11	Mar 30, 2020, 21:59:58	View Delete
inst-drds-console-drds-manager-xmw6x	Succeeded	Mar 30, 2020, 21:48:11	Mar 30, 2020, 21:53:39	View Delete
inst-drds-console-jingwei-console-x5kw6	Succeeded	Mar 30, 2020, 21:48:11	Mar 30, 2020, 22:02:23	View Delete
inst-drds-console-rtools-zw26b	Succeeded	Mar 30, 2020, 21:48:11	Mar 30, 2020, 21:51:42	View Delete
inst-drds-console-service-test-pwln9	Succeeded	Mar 30, 2020, 21:48:11	Mar 30, 2020, 22:03:55	View Delete
inst-middleware-zookeeper-zk-8wglh	Succeeded	Mar 30, 2020, 21:48:11	Mar 30, 2020, 21:49:23	View Delete
ark-3k3jj0kn82rjt63arvaf8emvgj.123456	Failed	Mar 30, 2020, 21:47:41	Mar 30, 2020, 22:04:19	View Delete Retry

9.1.6.2.6 Delete a task

You can delete a task on the Task Instances page. If a task is in the Running state, this operation will immediately terminate the task and delete the task record. If a task is in other states, this operation will immediately delete the task record.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Task Center** > **Task Instances**.
3. In the task instance list, find the target task. Click **Delete** in the **Actions** column.

9.1.7 Platform diagnostics

The PaaS console provides platform-level diagnostics. This module collects information about the console and products deployed in the console, presents summary diagnostic

results, and allows you to download detailed diagnostic results. The module aims to improve user experience of diagnostics.

9.1.7.1 Diagnostic items


The Diagnostic Items page displays all diagnostic items in the PaaS console. On this page, you can view, execute, and delete diagnostic items.

9.1.7.1.1 View a diagnostic item

You can view details about the current diagnostic item, such as the name, type, description, start time, deletion protection, and definition.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Platform Diagnostics > Diagnostic Items**.
3. Find the target diagnostic item. Click **View** in the **Actions** column.
4. In the pane that appears, view details of the diagnostic item.



The screenshot shows the 'View Diagnostic Item' interface. On the left, a sidebar lists several diagnostic items, each with a checkbox: `base_cmd_basic_cpu`, `base_cmd_basic_disk`, `base_cmd_basic_k8s`, `base_cmd_basic_mem`, `base_cmd_basic_other`, `base_logs_basic`, `base_logs_flaws_pods`, and `base_service_basic`. The main panel displays the details for a selected item:

- Start Time:** Mar 29, 2020, 18:55:54
- Deletion Protection:** Yes
- Definition:** A shell script snippet showing functions for collecting CPU info and a main function to execute the collection.

```

1 #!/usr/bin/env bash
2
3 - function collect_cpu_info() {
4     chroot "${CHROOT_DIR}" lscpu > $RESULTS_DIR/lscpu 2>&1
5     chroot "${CHROOT_DIR}" ps auxw|head -1;ps auxw|sort -rn -k3|head -10 > $RESULTS_DIR/ps_auxw_sort
6     chroot "${CHROOT_DIR}" ps auxw --sort=%cpu > $RESULTS_DIR/ps_auxw_sort
7
8     return 0
9 }
10
11 - function main() {
12     starttime=`date +%Y-%m-%d %H:%M:%S`
13     msg=''
14     type=''
15     level=''
16
17     collect_cpu_info
18 - if [ $? -eq 0 ]; then
19         status="pass"

```

9.1.7.1.2 Execute a diagnostic item

You can execute diagnostic items on the Diagnostic Items page.

Procedure

1. Log on to the PaaS console.

2. In the left-side navigation pane, choose **Platform Diagnostics > Diagnostic Items**.

3. Select one or more diagnostic items and click **Submit Diagnosis**.

<input checked="" type="checkbox"/>	base_logs_flaws_pods	Job	Mar 29, 2020, 18:55:54		View Delete
<input checked="" type="checkbox"/>	base_service_basic	DaemonSet	Mar 29, 2020, 18:55:54		View Delete
<input type="checkbox"/>	base_service_inner_db	Job	Mar 29, 2020, 18:55:54		View Delete
<input checked="" type="checkbox"/>	base_service_inner_coredns	Job	Mar 29, 2020, 18:55:54		View Delete
<div> <input type="checkbox"/> Submit Diagnosis </div> <div> Entries per Page: 10 ▼ Total Entries: 15 < 1 2 > </div>					

4. In the dialog box that appears, click **OK**.

9.1.7.1.3 Delete a diagnostic item

You can delete diagnostic items. You can only delete imported diagnostic items, but not the diagnostic items preset by the system.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Platform Diagnostics > Diagnostic Items**.
3. Find the target diagnostic item. Click **Delete** in the **Actions** column.
4. In the message that appears, click **OK**.

9.1.7.2 Diagnostic tasks

The Diagnostic Tasks page displays all diagnostic tasks. On this page, you can view diagnostic progress, view diagnostic reports, download diagnostic reports, terminate diagnostic tasks, and delete diagnostic tasks.


9.1.7.2.1 View diagnostic progress

After starting a diagnostic task, you can view the diagnostic progress on the **Diagnostic Tasks** page.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Platform Diagnostics > Diagnostic Tasks**.
3. Find the target diagnostic task. Click **Diagnostic Progress** in the **Actions** column.

4. On the **Diagnostic Progress** page, click task nodes in sequence to view the diagnostic progress and logs of the current diagnostic task.



9.1.7.2.2 View a diagnostic report

After a diagnostic task is completed, you can view the diagnostic report.

Prerequisites

Only when a diagnostic task is in the **Succeeded** state, you can view the diagnostic report.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Platform Diagnostics > Diagnostic Tasks**.
3. Find the target diagnostic task. Click **View Report** in the **Actions** column.
4. In the pane that appears, view the diagnostic results, such as the name, status, and details.

9.1.7.2.3 Download a diagnostic report

After a diagnostic task is completed, you can download the diagnostic report locally for offline query and analysis.

Prerequisites

You can only download the report for a diagnostic task in the **Succeeded** state.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Platform Diagnostics > Diagnostic Tasks**.
3. Find the target diagnostic task. Click **Download** in the **Actions** column.

9.1.7.2.4 Terminate a diagnostic task

You can terminate a diagnostic task which is in the Running state.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Platform Diagnostics > Diagnostic Tasks**.
3. Find the target diagnostic task. Choose **More > Terminate** in the **Actions** column.
4. In the message that appears, click **OK**.

9.1.7.2.5 Delete a diagnostic task

You can delete a diagnostic task which is no longer needed.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Platform Diagnostics > Diagnostic Tasks**.
3. Find the target diagnostic task. Choose **More > Delete** in the **Actions** column.
4. In the message that appears, click **OK**.

9.1.8 Alerts

The **Alerts** module implements unified management of alerts in the PaaS console. You can view alert rules, notification channels, and alert events. You can also configure alert rules and notification channels in the **Alerts** module.

9.1.8.1 Alert rule groups

An alert rule must belong to an alert rule group. You can create alert rule groups and add alert rules to alert rule groups.

9.1.8.1.1 Create an alert rule group

You can create alert rule groups based on business needs. When you create an alert rule group, you must add an alert rule to the group.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Alerts > Alert Groups**.

3. In the upper-right corner of the page, click **Create Rule Group**.
4. In the **Create Rule Group** dialog box that appears, configure the parameters.

Create Rule Group ✕

Rule Group Name

Alert Group Name

TTL

—

0

+

m

▼

Rule Name

Level

Select ▼

Message


Expression

Operator ▼

Aggregate Opera ▼

Built-in Function ▼

Parameter	Description
Rule Group Name	The globally unique name of the alert rule group.
Alert Group Name	The globally unique name of the alert group. An alert rule group must have an alert group.
TTL	Specifies the time period that an error lasts before an alert is sent. <ul style="list-style-type: none"> h: indicates hours. m: indicates minutes. s: indicates seconds.
Rule Name	The globally unique name of the alert rule.
Level	The severity of the alert. Valid values: <ul style="list-style-type: none"> Warning: indicates a warning alert. Critical: indicates a critical alert.
Message	The description of the alert.

Parameter	Description
Expression	<p>The criteria to trigger the alert.</p> <div>  Note: We recommend that you select operators, aggregate operations, or built-in functions from the drop-down lists if you want to use them in the expression. </div>

5. Click **Submit**.

9.1.8.1.2 Add an alert rule

After creating an alert rule group, you can add alert rules to this group.

Prerequisites

Confirm that an alert rule group has been created. For more information about how to create an alert rule group, see [Create an alert rule group](#).

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Alerts > Alert Groups**.
3. Find the target rule group. Click **Modify Rule** in the **Actions** column.

The **Rules** page is displayed. You can view all alert rules in the alert rule group.

Rules					Create Rule
Rule Name	TTL	Label	Annotations	Expression	Actions
AlertmanagerConfigInconsistent	5m	severity: critical	message: The configuration of the ...	count_values("config_hash", alertma...	Modify Delete
AlertmanagerFailedReload	10m	severity: warning	message: Reloading Alertmanager'...	alertmanager_config_last_reload_su...	Modify Delete
AlertmanagerMembersInconsistent	5m	severity: critical	message: Alertmanager has not fo...	alertmanager_cluster_members(job...	Modify Delete


4. In the upper-right corner of the page, click **Create Rule**.

5. In the **Create Rule** dialog box that appears, configure the parameters.

The screenshot shows the 'Create Rule' dialog box. It includes the following fields and controls:

- TTL:** A spinner control showing '0' and a unit dropdown menu showing 'm'.
- Rule Name:** A text input field.
- Level:** A dropdown menu with 'Select' as the current value.
- Message:** A text input field.
- Expression:** Three dropdown menus labeled 'Operator', 'Aggregate', and 'Built-in Functi', followed by a large text area for the expression.
- Submit:** A button at the bottom right.

Parameter	Description
TTL	Specifies the time period that an error lasts before an alert is sent. <ul style="list-style-type: none">• h: indicates hours.• m: indicates minutes.• s: indicates seconds.
Rule Name	The globally unique name of the alert rule.
Level	The severity of the alert. Valid values: <ul style="list-style-type: none">• Warning: indicates a warning alert.• Critical: indicates a critical alert.
Message	The description of the alert.

Parameter	Description
Expression	<p>The criteria to trigger the alert.</p> <div>  Note: We recommend that you select operators, aggregate operations, or built-in functions from the drop-down lists if you want to use them in the expression. </div>

6. Click **Submit**.


9.1.8.1.3 Modify an alert rule

You can modify alert rules based on business needs.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Alerts > Alert Groups**.
3. On the **Rule Groups** page, view all alert rule groups defined in the system.
4. Find the rule group for the target rule. Click **Modify Rule** in the **Actions** column.
5. On the **Rules** page, view all alert rules in this rule group.
6. Find the target rule. Click **Modify** in the **Actions** column.
7. Modify the TTL, Level, Message, and Expression parameters of the alert rule as needed.

Parameter	Description
TTL	<p>Specifies the time period that an error lasts before an alert is sent.</p> <ul style="list-style-type: none"> • h: indicates hours. • m: indicates minutes. • s: indicates seconds.
Level	<p>The severity of the alert. Valid values:</p> <ul style="list-style-type: none"> • Warning: indicates a warning alert. • Critical: indicates a critical alert.
Message	The description of the alert.

Parameter	Description
Expression	<p>The criteria to trigger the alert.</p> <div>  Note: We recommend that you select operators, aggregate operations, or built-in functions from the drop-down lists if you want to use them in the expression. </div>

8. Click **Submit**.

9.1.8.1.4 Delete an alert rule

You can delete an alert rule which is no longer needed from an alert rule group.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Alerts > Alert Groups**.
3. On the **Rule Groups** page, view all alert rule groups defined in the system.
4. Find the rule group for the target rule. Click **Modify Rule** in the **Actions** column.
5. On the **Rules** page, view all alert rules in this rule group.
6. Find the target rule. Click **Delete** in the **Actions** column.
7. In the message that appears, click **OK**.

9.1.8.1.5 Delete an alert rule group

You can delete an alert rule group that is no longer needed.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Alerts > Alert Groups**.

The **Rule Groups** page is displayed. You can view all alert rule groups defined in the system on this page.
3. Find the target rule group. Click **Delete** in the **Actions** column.
4. In the message that appears, click **OK**.

9.1.8.2 Notification channels

You can view and modify notification channel settings on the Notification Channels page.

9.1.8.2.1 View notification channel settings

You can view the current notification channel settings.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Alerts > Notification Channels**.
3. In the **Global Settings**, **Routing**, and **Receiver** sections, view the relevant information.

9.1.8.2.2 Modify notification channel settings

You can modify notification channel settings such as global settings, routing, and receivers.

9.1.8.2.2.1 Modify global settings

You can modify global settings such as `resolve_timeout`, `smtp_info`, and notifications.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Alerts > Notification Channels**.
3. In the upper-right corner of the page, click **Edit**.

4. In the **Global Settings** section, modify `resolve_timeout`, `smtp_info`, or notifications based on business needs.

Global Settings

resolve_timeout ?

—

5

+

m

▼

smtp_info

▲

Attribute Key

Attribute Value

smtp_from

smtp_smarthost

smtp_hello

smtp_auth_username

smtp_auth_password

smtp_auth_identity

smtp_auth_secret

smtp_require_tls

tru

notifications

Parameter	Description
resolve_timeout	Specifies the time period before an alert is marked as resolved if the Alertmanager does not receive such an alert further.

Parameter	Description
smtp_info	<p>Specifies global SMTP information.</p> <p>To modify this item, turn on the switch on the right and then click the show icon. You can modify the following parameters:</p> <ul style="list-style-type: none"> • smtp_from: the source email address for alerts. • smtp_smarthost: the SMTP server address and port for the source email address for alerts. Example: smtp_smarthosts:smtp.example.com:465 • smtp_hello: the default host name that identifies the SMTP server. • smtp_auth_username, smtp_auth_password: the username and password for the source email address for alerts. • smtp_auth_identity: uses the plain SMTP authentication. • smtp_auth_secret: uses the CRAM-MD5 SMTP authentication. • smtp_require_tls: the default SMTP TLS configuration. Although the default value is true, this parameter is usually set to false to avoid starttls errors which occur if the parameter is set to true.
notifications	<p>The Slack configuration.</p> <p>To modify this item, turn on the switch on the right and then click the show icon. You can modify the following parameters:</p> <ul style="list-style-type: none"> • slack_api_url: the API URL for Slack notifications. • victorops_api_key: the VictorOps API key. • victorops_api_url: the VictorOps API URL. • pagerduty_url: the destination URL for API requests. • opsgenie_api_key: the Opsgenie API key. • opsgenie_api_url: the destination URL for Opsgenie API request. • hipchat_api_url: the source URL for API requests. • hipchat_auth_token: the authentication token. • wechat_api_url: the WeChat API URL. • wechat_api_secret: the WeChat API key. • wechat_api_corp_id: the WeChat API corporate ID.

5. In the upper-right corner of the page, click **Save**.

9.1.8.2.2 Modify routing settings

You can modify global routing settings, and add or delete sub-routes.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Alerts > Notification Channels**.
3. In the upper-right corner of the page, click **Edit**.

4. In the **Routing section, perform the following operations:**

- Modify routing settings

Modify the default route or subroutes based on business needs.

Routing

Default Route

Attribute Key	Attribute Value
receiver	<input type="text" value="null"/>
group_wait	<input type="text" value="30s"/>
group_interval	<input type="text" value="5m"/>
repeat_interval	<input type="text" value="12h"/>
group_by	<input type="text" value="job"/>
continue	<input checked="" type="radio"/> Yes
match	<input type="button" value="Add"/>
match_re	<input type="button" value="Add"/>

Subroutes

Attribute Key

Attribute Value

receiver

group_wait

group_interval

repeat_interval

group_by

continue

☒ No

match

match_re

:

Parameter	Description
Default Route	<p>The global route. You can configure the route information based on the actual environment.</p> <ul style="list-style-type: none">- receiver: the name of the alert receiver.- group_wait: specifies the waiting time to initialize a message when a new alert group is created. This method ensures that the system can have enough time to get multiple alerts for the same alert group, and then trigger an alert message.- group_interval: specifies the waiting time to send a new alert message.- repeat_interval: specifies the waiting time to send an alert message again.- group_by: the tag list. It is the regrouping tag list after alert messages are received. For example, all received alert messages that contain the <code>cluster=A</code> and <code>alertname=LatncyHigh</code> tags are aggregated into a group.- continue: specifies whether an alert matches subsequent nodes.- match: Click Add and specify a receiver for matched alerts.- match_re: Click Add. Enter a regular expression and specify a receiver for alerts that match the regular expression.

Parameter	Description
Subroutes	<p>Configure subroutes in the similar way to the global route, so that you can export an alert type to other locations.</p> <ul style="list-style-type: none"> - receiver: the name of the alert receiver. - group_wait: specifies the waiting time to initialize a message when a new alert group is created. This method ensures that the system can have enough time to get multiple alerts for the same alert group, and then trigger an alert message. - group_interval: specifies the waiting time to send a new alert message. - repeat_interval: specifies the waiting time to send an alert message again. - group_by: the tag list. It is the regrouping tag list after alert messages are received. For example, all received alert messages that contain the cluster=A and alertname=LatncyHigh tags are aggregated into a group. - continue: specifies whether an alert matches subsequent nodes. - match: click Add. Enter the key and value of a tag and specify a receiver for alerts that match the tag. - match_re: click Add. Enter a regular expression based on the key and value of a tag and specify a receiver for alerts that match the regular expression.

- Add a subroute

To export an alert type to another location, you can click **Add Subroute** at the lower part of the **Routing** section to configure a new subroute.

- Delete a subroute

In the **Routing** section, find the target subroute and click the Delete icon to delete a subroute which is no longer needed.

Routing

Default Route ▼

Subroutes ▲ ☒

Attribute Key	Attribute Value
receiver	null
group_wait	
group_interval	
repeat_interval	
group_by	Separate multiple values
continue	<input checked="" type="radio"/> No
match	Add
match_re	Add

alertname : Watchdog

9.1.8.2.2.3 Modify receiver settings

You can create, modify, or delete alert receiver settings based on business needs.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Alerts > Notification Channels**.
3. In the upper-right corner of the page, click **Edit**.
4. In the **Receivers** section, perform the following operations:
 - Modify receiver settings

Modify the name and type of a receiver based on business needs.

Receivers Add Receiver

▼ null

Receiver Name null

Receiver Type Select

Parameter	Description
Receiver Name	The name of the alert receiver.

Parameter	Description
Receiver Type	<p>Valid values for Receiver Type: webhook and email.</p> <p>If Receiver Type is set to webhook, you must configure the following parameters:</p> <ul style="list-style-type: none"> - url: the URL of the alert receiver. - send_resolved: specifies whether to send messages for resolved alerts. Default value: No. <p>If Receiver Type is set to email, you must configure the following parameters:</p> <ul style="list-style-type: none"> - send_resolved: specifies whether to send messages for resolved alerts. Default value: No. - to: the destination email address for alerts. - from: the source email address for alerts. - smarthost: the server address and port for the source email address for alerts. - hello: the default host name that identifies the email server. - auth_username: the username for the source email address for alerts. - auth_password: the password for the source email address for alerts. - auth_secret: uses the CRAM-MD5 authentication. - auth_identity: uses the plain authentication. - require_tls: the default TLS configuration. Although the default value is Yes, this parameter is usually set to No to avoid starttls errors which occur if the parameter is set to Yes.

- Add a receiver

In the upper-right corner of the **Receivers** section, click **Add Receiver**. Configure the parameters.

- Delete a receiver

In the **Receivers** section, find the target receiver and click the Delete icon to delete a receiver which is no longer needed.

Receivers Add Receiver

▼ null 🗑️

Receiver Name

Receiver Type

Attribute Key	Attribute Value
url	<input type="text"/>
send_resolved	<input type="checkbox"/> No

Case

> Receiver 🗑️

9.1.8.3 Alert events

The Alert Events page displays all alert events and all aggregated alert events by alert or product name.

9.1.8.3.1 View aggregated alert events by alert name

On the **Alert Aggregation** tab, you can view aggregated alert events by alert name.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Alerts > Alert Events**.
The **Alert Aggregation** tab is displayed by default. This tab displays all aggregated alert events by alert name.
3. In the alert name view, the Alert Aggregation tab displays all aggregated alert events by alert name. The aggregated alert event list contains the following columns: Alert Name, Details, Total Alerts, Severity, and Actions.

Alert Aggregation | All Events Aggregate View Alert

Product Service Severity Start Date Search

Alert Name	Details	Total Alerts	Severity	Actions
CPUThrottlingHigh	100% throttling of CPU in namespace drds for container dr...	5	Warning	View
ProbeReadinessCheckFailed	ProbeReadiness check has failed for drds/drds-server-7dd...	2	Critical	View

4. Optional: In the search box at the top of the tab, set Product, Service, Severity, and Start Date, and then click **Search** to query aggregated alert events that meet the conditions.

- Find the target aggregated alert events. Click the number in the **Total Alerts** column or **View** in the **Actions** column to view details of individual alert events within the aggregated alert events.

The alert details list contains the following columns: Status, Start Time, End Time, Update Time, and Label.

Alert Details						
alertname: CPUThrottlingHigh message: 100% throttling of CPU in namespace drds for container drds-logger in pod drds-logger-0. metric: container_cpu_cfs_throttled_periods_total + container_cpu_cfs_periods_total product: acs service: ack-prometheus-operator						
Status	Start Time	End Time	Update Time	Label		
Active	Mar 30, 2020, 22:16:23	Mar 31, 2020, 14:40:23	Mar 31, 2020, 14:37:23	alertna...	contain...	namesp...
Active	Mar 31, 2020, 14:30:53	Mar 31, 2020, 14:39:53	Mar 31, 2020, 14:36:53	alertna...	contain...	namesp...
Active	Mar 31, 2020, 14:30:23	Mar 31, 2020, 14:39:23	Mar 31, 2020, 14:36:23	alertna...	contain...	namesp...

9.1.8.3.2 View aggregated alert events by product name

On the **Alert Aggregation** tab, you can view aggregated alert events by product name.

Procedure

- Log on to the PaaS console.
- In the left-side navigation pane, choose **Alerts > Alert Events**.

The **Alert Aggregation** tab is displayed by default. This tab displays all aggregated alert events by alert name.

- Turn off the **Aggregate View** switch to turn to the product name view.

In the product name view, the **Alert Aggregation** tab displays all aggregated alert events by product name.

Alert Aggregation All Events		Aggregate View Alert <input checked="" type="checkbox"/>		
Product <input type="text"/>	Service <input type="text"/>	Severity <input type="text"/>	Start Date <input type="text"/>	<input type="button" value="Search"/>
Alert Name	Details	Total Alerts	Severity	Actions
CPUThrottlingHigh	97% throttling of CPU in namespace drds for container drd...	6	Warning	View

- Optional: In the search box at the top of the tab, set Product, Service, Severity, and Start Date, and then click **Search** to query aggregated alert events that meet the conditions.

5. Find the target aggregated alert events. Click the number in the **Total Alerts** column or **View** in the **Actions** column to view details of individual alert events within the aggregated alert events.

The alert details list contains the following columns: Status, Start Time, End Time, Update Time, and Label.

9.1.8.3.3 View all alert events

On the **All Events** tab, you can view all alert events generated in the PaaS console.

Procedure

1. Log on to the PaaS console.
2. In the left-side navigation pane, choose **Alerts** > **Alert Events**.
3. Click the **All Events** tab.
4. The tab displays all alert events. The alert event list contains the following columns: Alert Name, Start Time, End Time, Update Time, Status, Details, Severity, and Label.

9.2 Harbor-based image repository console

9.2.1 Overview

This topic describes the features and purposes of Harbor.

The Harbor service is integrated into Apsara Stack Agility PaaS Kubernetes to provide a high -availability image repository and support image permission control, security scanning, and synchronization.

You can use Docker to push and pull images, as well as grant different image repository permissions to different roles.

Harbor 1.9.3 is an open-source tool. This documentation only provides basic instructions on image pushing and permission control. For more information about the features of Harbor, visit https://github.com/goharbor/harbor/blob/release-1.9.0/docs/user_guide.md.

9.2.2 Preparations

Before you use the Harbor-based image repository, you must obtain the domain name of the Harbor-based image repository and configure the host information.

9.2.2.1 Query the domain name of the Harbor-based image repository

After the environment is deployed, you can perform the following steps to query the domain name of the Harbor-based image repository:

Procedure

1. Log on to the master1 node.
2. Run the following command:

kubectl get ingress -n acs-harbor

```
[root@node2 ~]# kubectl get ingress -n acs-harbor
NAME                HOSTS                ADDRESS      PORTS      AGE
harbor-harbor-ingress  harbor.myk8s.paas.com  80          3d2h
[root@node2 ~]#
```

You can obtain the domain name of the Harbor-based image repository based on the returned result.

For example, if the returned result is `harbor.myk8s.paas.com`, the domain name of the Harbor-based image repository is `harbor.myk8s.paas.com:80`.

9.2.2.2 Configure host information

Before you use the Harbor-based image repository, you must perform a series of configurations to ensure that each machine in the cluster can access the Harbor-based image repository.

Add master1 node information

If the DNS of the machine accessing the Harbor-based image repository cannot resolve to the domain name of the repository, you must add the following content to the `/etc/hosts` file of the machine:

```
xx.xx.xx.xx harbor.myk8s.${domain}
```

In this example, the domain name of the Harbor-based image repository is `harbor.myk8s.paas.com`. You must add the following content to the `/etc/hosts` file:

```
xx.xx.xx.xx harbor.myk8s.paas.com
```

In the content, `xx.xx.xx.xx` is the IP address of the master1 node.

Configure insecure-registry for Docker

You must access the Harbor-based image repository over HTTP because Harbor does not have TLS enabled. If the current machine encounters HTTPS problems when attempting to use Docker to access the Harbor-based image repository, you can solve these problems by configuring `insecure-registry`.

This example shows how to configure `insecure-registry` for Linux machines. Follow these steps:

1. Log on to each node of the PaaS cluster separately.
2. Find the `daemon.json` file in the `/etc/docker/daemon.json` directory.
3. Add the domain name of the Harbor-based image repository to the `daemon.json` file.

An example of the result is as follows:

```
{
  "insecure-registries":[
    "harbor.myk8s.paas.com:80"
  ]
}
```

4. After the modification, run the following command to restart Docker:

systemctl restart docker

9.2.3 Log on to the Harbor-based image repository console

This topic describes how to log on to the Harbor-based image repository console.

Prerequisites

Before you log on to the Harbor-based image repository console, make sure that the following requirements are met:

- You have obtained the URL of the Harbor-based image repository console. For more information, see [Query the domain name of the Harbor-based image repository](#).
- You have obtained the username and password that are used to log on to the Harbor-based image repository console from the deployment personnel or administrator.
- We recommend that you use the Google Chrome browser.

Procedure

1. Enter the access URL of the Harbor-based image repository console in the address bar: `harbor.myk8s.${domain}:80`. Press the Enter key.



Note:

If you cannot access the Harbor-based image repository console, see [Configure host information](#).


2. Enter your username and password.



Note:

We recommend that you change your password immediately after you log on to the Harbor-based image repository console.

Method: In the upper-right corner of the page, click **Change Password**. Enter the current password and new password, and confirm the password. Click **OK**.



Harbor

Search Harbor...

Harbor

Username

Password

☐ Remember me [Forgot password](#)

LOG IN

3. Click **LOG IN**.


9.2.4 Create users

After logging on to the Harbor-based image repository console, an administrator must create users to meet different requirements for access control.

Procedure

1. Log on to the Harbor-based image repository console as an administrator.
2. In the left-side navigation pane, choose **Administration > Users**.
3. On the **Users** page, click **NEW USER**.

4. In the **New User** dialog box that appears, set Username, Email, First and last name, Password, Confirm Password, and Comments. Click **OK**.

A screenshot of a 'New User' dialog box. It has a title 'New User' at the top left. Below the title are six input fields: 'Username *' with the value 'info', 'Email *' with the value 'info@example.com', 'First and last name *' with the value 'infotest', 'Password *' with masked characters '.....', 'Confirm Password *' with masked characters '.....' and a cursor, and 'Comments' which is empty. At the bottom right are two buttons: 'CANCEL' and 'OK'.

9.2.5 Create projects

Projects are containers that store image repositories. You must create a project before you can push or pull images.

Procedure

1. Log on to the Harbor-based image repository console as an administrator.
2. In the left-side navigation pane, click **Projects**.
3. On the **Projects** page, click **NEW PROJECT**.
4. In the **New Project** dialog box that appears, configure the following parameters.

Parameter	Description
Project Name	The name of the project to be created.

Parameter	Description
Access Level	The access level of the project. Whether the project is public determines whether permissions are required to pull images from the image repository. If Public is selected, all users including unlogged users are allowed to use Docker to pull images.
Count quota	The maximum number of images that can be stored in the image repository. The default value is -1 , indicating that no upper limit is set on the number of images that can be stored in the image repository.
Storage quota	The storage capacity of the image repository. The default value is -1 , indicating that no upper limit is set on the storage capacity of the image repository.

New Project

Project Name *

info_library

Access Level

☐ Public ⓘ

Count quota *

10000 ⓘ

Storage quota *

500 GB ⓘ

CANCEL

OK

5. Click **OK**.

By default, the creator of the project is the project administrator.

9.2.6 Grant project permissions

After creating a user and a project, you must grant the user project permissions so that the user can access the project.

Prerequisites

- A user is created. For more information about how to create a user, see [Create users](#).
- A project is created. For more information about how to create a project, see [Create projects](#).

Procedure

1. Log on to the Harbor-based image repository console as an administrator.
2. In the left-side navigation pane, click **Projects**.
3. In the project list, find the project you just created and click the project name.
4. Click the **Members** tab.
5. Click **+ USER**.
6. In the **New Member** dialog box that appears, configure the following parameters.

Parameter	Description
Name	Enter the name of the user to whom you want to grant project permissions. For example, you can enter the name of the user you just created.

Parameter	Description
Role	<p>Valid values:</p> <ul style="list-style-type: none"> • Project Admin: This role has all project permissions such as those to push images, pull images, and configure the project. • Master: This role has the permissions to push images and pull images. • Developer: This role has the permissions to push images and pull images. • Guest: This role has the permission to pull images.

New Member

Add a user to be a member of this project with specified role

Name *

info

Role

☒ Project Admin

☐ Master

☐ Developer

☐ Guest

CANCEL

OK

7. Click **OK**.

9.2.7 Push images

To deploy your applications on the cloud, you must push images to the Harbor-based image repository.

Prerequisites

Before you push images, make sure that the following requirements are met:

- You have the permission to push images as a project administrator, maintenance personnel, or developer.
- The image to be pushed is available. It can be a local image or an image downloaded from another image repository.


**Note:**

- The Harbor-based image repository does not support images with manifest v2 schema 1.
- The Harbor-based image repository limits the size of an image layer to 5,000 MB. If this limit is exceeded, the image will fail to be uploaded. If an image layer is larger than 5,000 MB in size, reduce the size of the image.

Procedure

1. In the left-side navigation pane of the Harbor-based image repository console, click **Projects**.
2. In the project list, find the project to which you want to push the image and click the project name.
3. Click the **Repositories** tab.
4. In the upper-right corner of the page, click **PUSH IMAGE**.

The command used to push images is displayed.

**Note:**

The specific domain name of the image repository to which you push images varies with the environment. This topic uses the domain name harbor.myk8s.paas.com:80 of the Harbor-based image repository as an example.

5. Tag and push the image by using the displayed commands.

- a) Log on to the master1 node.
- b) Prepare the image to be pushed in the local environment.
- c) Run the following command to tag the image.

In this example, the 1.13.3-k8s tag is added to the info_library/nginx image repository.

```
docker tag info_library/nginx:1.13.3-k8s harbor.myk8s.paas.com:80/info_library/nginx:1.13.3-k8s
```

- d) Use the Docker command to log on to the image repository.

A. Run the following command to log on to the image repository:

```
docker login harbor.myk8s.paas.com:80
```

B. Enter the administrator account and password of the image repository.

After you log on to the image repository, **Login Succeeded** is displayed.

**Notice:**

If the system prompts that the certificate verification failed during logon, you must refer to [Configure host information](#) to complete the configuration of insecure-registry.

- e) After you log on to the image repository, run the following command to push the tagged image to the current project:

```
docker push harbor.myk8s.paas.com:80/info_library/nginx:1.13.3-k8s
```

- 6.** Wait a few minutes and then log on to the Harbor-based image repository console again. On the **Projects** page, the value of **Repositories Count** corresponding to the **info_library** project is displayed as 1.

+ NEW PROJECT		x DELETE		All Projects	
<input type="checkbox"/>	Project Name	Access Level	Role	Repositories Count	Creation Time
<input type="checkbox"/>	info_library	Public	Project Admin	1	3/30/20, 5:39 PM
<input type="checkbox"/>		Public	Project Admin	1	3/30/20, 6:49 AM
<input type="checkbox"/>		Public	Project Admin	2	3/12/20, 6:22 PM

- 7.** Click the project name. On the page that appears, click the **Repositories** tab to view the pushed image.

8. Click the image name to view the image tag.

info_library/nginx

[Info](#)
[Images](#)

SCAN

COPY DIGEST

+ADD LABELS

RETAG

× DELETE

Q | ↺

<input type="checkbox"/>	Tag	Size	Pull Command	Vulnerability
<input type="checkbox"/>	1.13.3-k8s	12.05MB		Not Scanned

10 Operations of basic cloud products

10.1 ApsaraDB for RDS

10.1.1 Architecture

10.1.1.1 System architecture

10.1.1.1.1 Backup system

ApsaraDB for RDS can back up databases at any time and restore them to any point in time based on the backup policy, making the data more traceable.

Automatic backup

ApsaraDB RDS for MySQL supports both physical and logical backup.

You can flexibly configure the backup start time based on the service off-peak hours. All backup files are retained for seven days.

Log management

ApsaraDB RDS for MySQL automatically generates binlogs and allows you to download them for local incremental backup.

Instance cloning

A cloned instance is a new instance with the same content as the primary instance, including data and settings. This feature allows you to restore data of the primary instance or create multiple instances that are the same as the primary instance.

10.1.1.1.2 Monitoring system

RDS provides multi-dimensional monitoring services across the physical, network, and application layers to ensure business availability.

Performance monitoring

RDS provides nearly 20 metrics for system performance monitoring, such as disk capacity, IOPS, connections, CPU utilization, network traffic, TPS, QPS, and cache hit rate. You can obtain the running status information for any instances within the past year.

SQL auditing

The system records the SQL statements and related information sent to RDS instances, such as the connection IP address, database name, access account, execution time, and number of records returned. You can use SQL auditing to check instance security and locate problems.

Threshold alerts

RDS provides alert SMS notifications if status or performance exceptions occur in the instance.

These exceptions can be involved in instance locking, disk capacity, IOPS, connections, and CPU. You can configure alert thresholds and up to 50 alert recipients (of which five are effective at a time). When an instance exceeds the threshold, an SMS notification is sent to the alert recipients.

Web operation logs

The system logs all modification operations in the RDS console for administrators to check. These logs are retained for a maximum of 30 days.

10.1.1.1.3 Control system

If a host or instance does not respond, the RDS high-availability (HA) component checks for exceptions and fails over services within 30 seconds to guarantee that applications run normally.

10.1.1.1.4 Task scheduling system

You can use the RDS console or API operations to create and delete instances, or switch instances between the internal network and Internet. All instance operations are scheduled, traced, and displayed as tasks.

10.1.2 Log on to the Apsara Stack Operations console


Prerequisites

- ASO access address in the format of `http://region-id.aso.intranet-domain-id.com`.
- Google Chrome browser (recommended).

Procedure

1. Open the browser.

2. Enter the ASO access address `http://region-id.aso.intranet-domain-id.com` in the address bar and then press Enter.

The image shows a dark-themed login interface. At the top, the text "Log On" is displayed in a light blue font. Below this, there are two input fields. The first field is preceded by a user icon and the placeholder text "Enter a user name". The second field is preceded by a lock icon and the placeholder text "Enter the password". At the bottom of the form is a large blue button with the text "Log On" in white.

Note:

You can select the language from the drop-down list in the upper-right corner to change the language of ASO.

3. Enter the correct username and password.



Note:

Obtain the username and password used to log on to ASO from the deployment personnel or the administrator.

- The system has three default users:
 - Security officer: manages other users or roles.
 - Auditor officer: views audit logs.
 - System administrator: used for other functions except those of the security officer and auditor officer.
- You must modify the password of your username as instructed when you log on to ASO for the first time. To improve security, the password must be 10-20 characters long and can contain English uppercase/lowercase letters (A-Z or a-z), numbers (0-9), and special characters, such as exclamation points (!), at signs (@), number signs (#), dollar signs (\$), and percent signs (%), which meets the minimum complexity requirements.

4. Click **Log On** to log on to ASO.

10.1.3 Instance management

You can view instance details, logs, and user information.

Procedure

1. [Log on to the Apsara Stack Operations console](#).
2. In the left-side navigation pane, choose **Products > RDS**.
3. On the **Instance Management** tab of **RDS**, you can perform the following operations:
 - View instances

View instances that belong to the account on the **Instance Management** tab, as shown in [Figure 10-1: Instances](#).

Figure 10-1: Instances

Instance Name	Availa...	CPU Perfor...	QPS Perfor...	IOPS Perfor...	Conne...	Disk Usage	Instance Status	Datab... Type	Actions
...	Yes				0		Creating	mysql	User Information Create Backup
...	Yes		2 %		0		Using	redis	User Information Create Backup

- View instance details

Click the ID of an instance to view details, as shown in [Figure 10-2: Instance details](#). You can switch your service between primary and secondary instances and query history operations on this page.



Note:

If data is not synchronized between the primary and secondary instances, a forced switchover may result in data loss. Proceed with caution.

Figure 10-2: Instance details

Backup ID: [redacted]

Instance Name: [redacted] Database: mysql 5.6

Backup Switch: On No Persistent Backup: No Persistent Data

Retention Days: 30 Estimated Time: [redacted]

Database List: All Databases Backup Time: 18:00

Backup Status: Not Started Next Backup: Sep 27, 2019, 18:00:00

Backup Method: Physical Backup Backup Type: Full Backup

Secondary Server IP: [redacted] IDC: [redacted]

Backup Start At: - Backup Uploading Start At: -

Backup Source: Secondary Database Only Log Uploading Start At: Sep 5, 2019, 17:36:12

Backup Compression: Table Compression

Backup Period: ☒ Monday ☒ Tuesday ☒ Wednesday ☒ Thursday ☒ Friday ☒ Saturday ☒ Sunday

Note: [text area]

Create Single Database Backup

- **View user information**

On the Instance Management tab, click **User Information** in the **Actions** column corresponding to an instance, as shown in [Figure 10-3: User information](#).

Figure 10-3: User information

User Information: [redacted]

Instance Name	Instance Status	Database Type	Instance Usage Type	CPU Utilization	IOPS Utilization	Disk Utilization	Connections Utilization
[redacted]	CREATING	Redis	[redacted]	[redacted] %	[redacted] %	[redacted] %	[redacted] %
[redacted]	CREATING	Redis	[redacted]	[redacted] %	[redacted] %	[redacted] %	[redacted] %
[redacted]	CREATING	Redis	[redacted]	[redacted] %	[redacted] %	[redacted] %	[redacted] %
[redacted]	CREATING	Redis	[redacted]	[redacted] %	[redacted] %	[redacted] %	[redacted] %
[redacted]	CREATING	Redis	[redacted]	[redacted] %	[redacted] %	[redacted] %	[redacted] %
[redacted]	CREATING	Redis	[redacted]	[redacted] %	[redacted] %	[redacted] %	[redacted] %
[redacted]	CREATING	Redis	[redacted]	[redacted] %	[redacted] %	[redacted] %	[redacted] %

- **Create backups**

For ApsaraDB RDS for MySQL instances, click **Create Backup** in the **Actions** column to view the backup information, as shown in [Figure 10-4: Backup information](#). You can

also click **Create Single Database Backup** on the Backup Information page to back up a single database.

Figure 10-4: Backup information

Backup ID: [redacted]

Instance Name: [redacted]	Database: mysql 5.6
Backup Switch: On	No Persistent Backup: No Persistent Data
Retention Days: 30	Estimated Time: [redacted]
Database List: All Databases	Backup Time: 18:00
Backup Status: Not Started	Next Backup: Sep 27, 2019, 18:00:00
Backup Method: Physical Backup	Backup Type: Full Backup
Secondary Server IP: [redacted]	IDC: [redacted]
Backup Start At: -	Backup Uploading Start At: -
Backup Source: Secondary Database Only	Log Uploading Start At: Sep 5, 2019, 17:36:12
Backup Compression: Table Compression	
Backup Period: <input checked="" type="checkbox"/> Monday <input checked="" type="checkbox"/> Tuesday <input checked="" type="checkbox"/> Wednesday <input checked="" type="checkbox"/> Thursday <input checked="" type="checkbox"/> Friday <input checked="" type="checkbox"/> Saturday <input checked="" type="checkbox"/> Sunday	
Note: [text area]	

Create Single Database Backup

10.1.4 Manage hosts

You can view and manage hosts.

Procedure

1. Log on to the [Apsara Stack Operations console](#).
2. In the left-side navigation pane, choose **Products > RDS**.
3. On the **Host Management** tab of **RDS**, you can view all host information.

RDS							
Instance Management				Host Management			
Host Name	Host Status	Subdomain	Cluster Name	Host IP	Host ID	Database Engine Version	Database Engine
[redacted]	Normal offline	cn-qingdao-env8d-d01	[redacted]	[redacted]	1	5.6	MySQL
[redacted]	Normal offline	cn-qingdao-env8d-d01	[redacted]	[redacted]	2	5.6	MySQL
[redacted]	Normal offline	cn-qingdao-env8d-d01	[redacted]	[redacted]	3	5.6	MySQL
[redacted]	Normal offline	cn-qingdao-env8d-d01	[redacted]	[redacted]	4	5.6	MySQL

- Click a hostname to go to the **RDS Instance** page. You can view all instances on this host.

Instance Lock Mode	O&M End Time	Instance Type	RDS Instance ID	Instance ID	Instance Specification Code	Temporary Instance	Host ID	Instance Link Type	Database Engine	Instance Name	Instance Disk Storage	RDS Instance Port	O&M Start Time	Associated UID	Instance Role	Database Engine Version	Instance Status
No data is available																	

10.1.5 Security maintenance

10.1.5.1 Network security maintenance

Network security maintenance consists of device and network security maintenance.

Device security

Check network devices and enable their security management protocols and configurations of devices.

Check for timely updates to secure versions of network device software.

For more information about the security maintenance method, see the device documentation.

Network security

Based on your network considerations, select the intrusion detection system (IDS) or intrusion prevention system (IPS) to detect abnormal Internet and Intranet traffic and protect against attacks.

10.1.5.2 Account password maintenance

Account passwords include RDS system passwords and device passwords.

To ensure account security, you must periodically change the system and device passwords, and use passwords with high complexity.

11 Apsara Opsapi Management system

11.1 Apsara Opsapi Management system overview

This topic describes the features and infrastructure of the Apsara Opsapi Management system (Opsapi).

The Apsara Opsapi Management system is a platform that manages O&M APIs and SDKs in the Apsara Stack environment in a centralized manner. This system also manages API and SDK versions.


Most Apsara Stack products provide APIs for tenants. Only a few Apsara Stack products provide APIs for O&M. To address the business needs at the O&M level and meet custom development requirements of users such as developing their own O&M consoles or obtaining O&M data, Alibaba Cloud provides the Apsara Opsapi Management system.

The Apsara Opsapi Management system has the following features:

- Provides APIs at the system level and typical APIs for resource usage, monitoring, and alerting.
- Manages APIs, including querying, editing, testing, and deleting APIs.
- Provides an API designer to customize an API flow based on the existing API, which facilitates custom business.
- Manages versions and relationships between these versions. These versions include Apsara Stack versions, product versions, SDK versions, and API versions.
- Supports SDKs. The Apsara Opsapi Management system provides SDKs for Java and Python to call O&M APIs.

Figure 11-1: Infrastructure of the Apsara Opsapi Management system shows the infrastructure of the Apsara Opsapi Management system.

Figure 11-1: Infrastructure of the Apsara Opsapi Management system



The Apsara Opsapi Management system contains the following components:

- api-server: contains O&M APIs that are available in SDKs.
- API Portal: the O&M console used to manage Opsapis.
- api-node: the API designer.

11.2 Log on to the Apsara Opsapi Management system

The Apsara Opsapi Management system provides basic platform management functions for O&M engineers. These functions include API management, version management, test management, and system management. This topic describes how to log on to the Apsara Opsapi Management system.


Prerequisites

- ASO access address in the format of `http://region-id.aso.intranet-domain-id.com`.
- Google Chrome browser (recommended).

Procedure

1. Open the browser.

2. Enter the ASO access address `http://region-id.aso.intranet-domain-id.com` in the address bar and then press Enter.

The image shows a dark-themed login interface. At the top, the text "Log On" is displayed in a light blue font. Below this, there are two input fields. The first field is preceded by a user icon and contains the placeholder text "Enter a user name". The second field is preceded by a lock icon and contains the placeholder text "Enter the password". At the bottom of the form is a large blue button with the text "Log On" in white.

Note:

You can select the language from the drop-down list in the upper-right corner to change the language of ASO.

3. Enter the correct username and password.



Note:

Obtain the username and password used to log on to ASO from the deployment personnel or the administrator.

- The system has three default users:
 - Security officer: manages other users or roles.
 - Auditor officer: views audit logs.
 - System administrator: used for other functions except those of the security officer and auditor officer.
- You must modify the password of your username as instructed when you log on to ASO for the first time. To improve security, the password must be 10-20 characters long and can contain English uppercase/lowercase letters (A-Z or a-z), numbers (0-9), and special characters, such as exclamation points (!), at signs (@), number signs (#), dollar signs (\$), and percent signs (%), which meets the minimum complexity requirements.

4. Click **Log On** to log on to ASO.

5. In the left-side navigation pane, click **Products**.

6. In the **Apsara Stack O&M** section, click **Opsapi**.

11.3 API management

The Apsara Opsapi Management system provides APIs of various products in the Apsara Stack environment. You can manage these APIs, such as uploading, querying, editing, testing, and deleting APIs. You can also use the API designer to customize APIs.

11.3.1 Register APIs

An API can be defined in an XML file. Each API corresponds to one XML file. You can upload an XML file to register an API in the Apsara Opsapi Management system.

Context

The following fields must be defined in an XML file:

- API name
- namespace (or product name)
- API type
- Parameter

When you upload APIs, you can upload one or more XML files simultaneously. You must compress the XML files into a ZIP file before you upload these files.

Procedure

1. [Log on to the Apsara Opsapi Management system](#).
2. In the left-side navigation pane, choose **API Platform > APIs**. The **APIs** page appears.
3. In the upper-right corner, click **Upload API**. Select the XML or ZIP file to be uploaded.

After you upload the XML or ZIP file, you can view the uploaded APIs in the API list on the **APIs** page.

11.3.2 Modify information about APIs


You can modify basic information and specific parameters of an API.


Procedure

1. [Log on to the Apsara Opsapi Management system](#).
2. In the left-side navigation pane, choose **API Platform > APIs**. The **APIs** page appears.

3. Optional: Select a product from the **Select Product** drop-down list. Enter an API name in the search box.

You can enter a full or partial API name to search for APIs.

4. Click the  icon in the **Actions** column corresponding to the API to be modified.



5. In the Edit API dialog box that appears, click the **Basic Information** tab, modify the basic information, and then click **Save**.

The following table describes parameters of an API.

Parameter	Description
API Name	The name of the API.
Type	<p>The type of the API. Different products have different API types. The types are as follows:</p> <ul style="list-style-type: none"> opsAPI: the API for O&M OpenAPI: the API for product operations customAPI: the API customized through the API designer
Namespace	The namespace of the API that corresponds to the product name.
Endpoint	The domain name of the product that corresponds to the API.

6. Click the **Edit Parameters** tab to modify configuration information such as the request parameters, response parameters, and error handling mechanism.


Follow these steps: Set the request parameters in the **Parameters** section, response parameters in the **ResultMapping** section, and error handling mechanism in the **ErrorMapping** section.

7. After the modification is completed, click **Save**.

11.3.3 Test APIs

The Apsara Opsapi Management system allows you to test APIs online to check whether an API is available. During the test, you can save input parameters as a test case for subsequent execution.

Procedure

1. [Log on to the Apsara Opsapi Management system](#).
2. In the left-side navigation pane, choose **API Platform > APIs**. The **APIs** page appears.
3. On the APIs page, click the  icon in the **Actions** column corresponding to the API to be tested.
4. In the Test API dialog box, set **Request Parameters**.

Request parameters may vary with APIs. The following table describes the typical request parameters.

Parameter	Required	Description
regionId	Yes	The region ID of the test environment.
accessKeyId and accessKeySecret	Yes	The identification of the visitor. You can obtain them from the Apsara Stack console.

5. After request parameters are configured, click **Send**.

The Apsara Opsapi Management system sends a corresponding test request to the configured domain name. The response appears in the **Responses** section.

6. Optional: After the test is complete, click **Save As Test Case** for subsequent execution of this test case. You can do this by choosing **Testing Platform > Test Cases** on the Test Cases page.


11.3.4 Remove information about APIs

You can remove information about an API that you no longer need.

Procedure

1. [Log on to the Apsara Opsapi Management system.](#)
2. In the left-side navigation pane, choose **API Platform > APIs**. The **APIs** page appears.
3. Optional: Select a product from the **Select Product** drop-down list. Enter an API name in the search box.

You can enter a full or partial API name to search for APIs.

4. Click the  icon in the **Actions** column corresponding to the API to be removed.
5. In the message that appears, click **OK**.

11.3.5 API design

The Apsara Opsapi Management system provides an API designer to help you customize APIs.

11.3.5.1 API designer

This topic describes the API designer.

If Apsara Stack Opsapis do not match the APIs you are using, or if you need to customize APIs to meet the requirements of specific projects, you can use an API designer to assemble and create desired APIs in the flow design process.

The API designer is built based on the open-source project Node-RED. Node-RED is a powerful tool launched by IBM to build Internet of Things (IoT) applications. It uses the visual programming method that allows developers to connect predefined code blocks (nodes) to perform tasks. Connected nodes are a combination of input nodes, processing nodes, and output nodes. When they are connected to form a flow, they are able to process requests such as HTTP requests.

Node-RED is highly capable of customizing flows and processing HTTP messages. These capabilities can be easily expanded.

To design an API, follow these steps:

1. [Log on to the Apsara Opsapi Management system.](#)
2. In the left-side navigation pane, choose **API Platform > API Design**. The **API Designer** page appears.

3. Drag and drop the components on the left to the flow chart section. You can combine these components to complete a specific flow chart and design an API.

11.3.5.2 Designer nodes

This topic describes typical nodes that are used in the designer.

To customize Opsapis, the Apsara Opsapi Management system adds some nodes through the mechanism provided by Node-RED.

Typical nodes are described as follows:

- **api-request**: used to create a request to access an Opsapi. There is a small icon before each node. After you click the icon, a request is sent to the flow that contains the node.
- **api response**: used to provide responses and format the returned data.
- **api selector**: used to select and execute an existing API.
- **db exec**: used to execute a specified SQL operation.
- **new api**: used to create an API that contains a specified endpoint and specific input parameters.
- **sync msg**: used to synchronize multiple requests. Multiple responses are merged into one response.
- **py function**: Python is used in some modules during the API design process.
- **Input components**: detailed operations involved in a request process. For example, set the protocol type of a request to HTTP, TCP, or UDP, and specify the status code and created link for the request.
- **Output components**: the returned data, status code, and protocol in the response. Output components are used to describe fixed output modes such as request and response methods and formats of returned data.

11.3.5.3 Design an API flow

This topic describes how to design an API flow.

Each customized API has its own API flow. Each API flow consists of multiple connected nodes, including one input node, several processing nodes, and one return node (or output node).

Among the nodes:

- Typical input nodes are **api request** and **http in**.
- Typical return nodes are **api response** and **http response**.

- Typical processing nodes are **function**, **api selector**, and **db exec**. The **function** node is used to convert parameters and process simple logic.

An API flow is designed as follows:

1. Select an input node and an output node, and add processing nodes to the flow.
2. Specify the name and configurations of each node, such as the endpoint of the input node.
3. Connect the nodes as needed to form a flow.
4. In the upper-right corner of API Designer, click **Deploy** to publish the flow.
5. Access this flow in the browser. You can obtain the response.

11.4 Version management

11.4.1 Apsara Stack version management

Apsara Stack has multiple versions that vary with projects.

11.4.1.1 Add information about versions

You can add information about Apsara Stack versions as needed to manage the relationships among Apsara Stack versions, products, and product versions.

Context

Each Apsara Stack version can have either one release version or one snapshot of the on-premises environment or deployment environment. It can be distinguished by its version name and description.

Procedure

1. [Log on to the Apsara Opsapi Management system](#).
2. In the left-side navigation pane, choose **Versions > Apsara Stack Versions**. The **Apsara Stack Versions** page appears.
3. In the upper-right corner of the page, click **Add Version**.
4. In the **Add Version** dialog box that appears, set **Apsara Stack Version**, **Version**, and **Release Notes**.

We recommend that you enter information that is related to the current version for Release Notes.

5. Click **Submit**.

11.4.1.2 Select products for an Apsara Stack version

After you add information about an Apsara Stack version, you can select products that are supported in an Apsara Stack version based on version output conditions.

Procedure

1. [Log on to the Apsara Opsapi Management system.](#)
2. In the left-side navigation pane, choose **Versions > Apsara Stack Versions**. The **Apsara Stack Versions** page appears.
3. In the version list, click **Configure Products** in the Product column corresponding to the specified Apsara Stack version.
4. In the Configure Products dialog box that appears, select a version from the **Version** drop-down list and select the check box in the **Output** column corresponding to the product.

Configure Apsara Stack Products: 3.3
✕

Product	Version	Output
Ecs	3.1.0 ▼	<input checked="" type="checkbox"/>
Rds	3.1.0 ▼	<input checked="" type="checkbox"/>
Oss	2.4.2 ▼	<input type="checkbox"/>
Vpc	3.4.0 ▼	<input checked="" type="checkbox"/>
Slb	3.4.0 ▼	<input checked="" type="checkbox"/>

submit

5. Click **Submit** to generate information of the products of the specified Apsara Stack version.

11.4.1.3 Compare versions

You can use the version comparison function to compare the product differences between two Apsara Stack versions. Based on these product differences, you can further learn about the differences of their APIs as well as of the definitions and parameters of these APIs.

Context

- Apsara Stack version: Each Apsara Stack version can have either one release version or one snapshot of the on-premises environment or deployment environment. Versions are distinguished by its version name and description.
- Product version: the specific version of a product when each Apsara Stack version is released, such as RDS 3.7.0. An Apsara Stack release version can have only one version of a specific product.

Procedure

1. [Log on to the Apsara Opsapi Management system.](#)
2. In the left-side navigation pane, choose **Versions > Apsara Stack Versions**. The **Apsara Stack Versions** page appears.
3. In the upper-left corner of the page, click **Compare Versions**.
4. On the **Select Version** tab, select two versions to be compared, and click **Next**.

Select Source Version	Select Target Version
v3.3	v3.3
v3.4	v3.4
v3.5	v3.5
v3.6	v3.6
v3.7	v3.7
v3.8	v3.8

5. On the **Version Differences** tab, you can compare the product differences between the two versions. For example, you can view versions for which product information has been added or removed.
6. Click a product. Click **Next** to go to the **Product Differences** tab. You can compare the differences in product APIs between these two versions.

You can view functions for which APIs have been added or removed, and APIs remain the same in these two versions.

Compare Apsara Stack Versions

Select Version

Version Differences

3 Product Differences

4 Compare API Versions


ProductVpc-innerSource Version: N/A, Target Version: 807
APIs Added:801 ., APIs Deleted:0 ., APIs Changed:0 ., APIs Unchanged:0 .

Function Name	Source Version	Target Version	Status	Mark
CountCloudInstances			2016-04-28	new Added
DescribeNetworkQuotas			2016-04-28	new Added
GaFillParams			2016-04-28	new Added
GaFillProduct			2016-04-28	new Added
GaNotifyPaid			2016-04-28	new Added

Previous

Next


7. Click an API. Click **Next** to view the changes that are made to this API.



11.4.1.4 Remove information about Apsara Stack versions

If you no longer need the Apsara Stack version, you can remove its version and output information.

Procedure



1. [Log on to the Apsara Opsapi Management system.](#)
2. In the left-side navigation pane, choose **Versions > Apsara Stack Versions**. The **Apsara Stack Versions** page appears.
3. Click the  icon in the **Actions** column corresponding to the Apsara Stack version information about which is to be removed.
4. In the message that appears, click **OK**.

11.4.2 Product baseline management

Product baselines are a set of configurations used by Apsara Stack products to define products, services, service roles, and applications. The Apsara Opsapi Management system provides basic information about products, services, and service roles. During initialization, the Apsara Opsapi Management system automatically scans all product

baseline information in the Apsara Stack environment. You can use the system to scan the metadatabases and servers of services and service roles.

Procedure

1. [Log on to the Apsara Opsapi Management system.](#)
2. In the left-side navigation pane, choose **Versions > Product Baselines**. The **Product Baselines** page appears.
3. Follow these steps:
 - In the upper-right corner of the page, click **Scan Apsara Stack Environment** to scan metadatabases and servers that correspond to all products and update their information in the system.
 - Select a product from the drop-down list to query the service and service roles of the product.
 - Click the  icon in the **Actions** column corresponding to the service role to scan the metadatabases of the service role.
 - Select a service role. click the  icon in the **Actions** column corresponding to the service role to scan the server of the service role.

11.4.3 Product management

Operations and maintenance engineers can manage information of current Apsara Stack versions and product versions in real time.

Context

- Apsara Stack version and product version: Each Apsara Stack version can have only one specific version of products.
- Product version and SDK version: Each product version can have one SDK version.

11.4.3.1 Add information about products

You can add information about a product you need to manage.

Procedure


1. [Log on to the Apsara Opsapi Management system.](#)
2. In the left-side navigation pane, choose **Versions > Products**. The **Products** page appears.
3. In the upper-right corner of the page, click **Add Product**.
4. In the **Add Product** dialog box that appears, set **Product Name** and **Product Description**.

5. Click **Submit** to add information about a product.

11.4.3.2 Add information about product versions

After you add information about a product, you need to add its product version and API version information for subsequent version management.

Procedure

1. [Log on to the Apsara Opsapi Management system.](#)
2. In the left-side navigation pane, choose **Versions > Products**. The **Products** page appears.
3. On the Products page, click the  icon in the **Actions** column corresponding to the product about which the version information is to be added.
4. In the **Add Version** dialog box that appears, set **Version** and **API Version**.


Parameter	Description
Version	The version of the current product.
API Version	The API version of the current product.

5. Click **Submit**.

11.4.3.3 Import information about APIs

You can import information about a preset API to the Apsara Opsapi Management system.


Procedure

1. [Log on to the Apsara Opsapi Management system.](#)
2. In the left-side navigation pane, choose **Versions > Products**. The **Products** page appears.
3. In the product list, click the  icon in the **Actions** column corresponding to the product to be managed.
4. In the dialog box that appears, select the product version from the left drop-down list.

If information about the API has been imported for the product version, this API is displayed in the APIs section.

5. In the upper-right corner, click **Import API**.

6. In the Import API dialog box that appears, set **Apsara Stack Version** and **API File**.




7. Click **OK** to import the API to the system.

11.4.3.4 Set SDK versions

A product has multiple SDK versions. You can set the SDK version of a product to obtain the SDK version of the product in the Apsara Stack release version.

Procedure


1. [Log on to the Apsara Opsapi Management system.](#)
2. In the left-side navigation pane, choose **Versions > Products**. The **Products** page appears.
3. In the product list, click the  icon in the **Actions** column corresponding to the product of which the SDK version is to be modified.
4. In the **SDK Settings** dialog box that appears, click **Modify** in the **Actions** column corresponding to the product version.
5. Select the specified SDK version from the drop-down list. Click **Submit** in the **Actions** column corresponding to the SDK version. The SDK version is modified.

11.4.3.5 Modify product names and descriptions

You can modify the name and description of a product.

Procedure


1. [Log on to the Apsara Opsapi Management system.](#)
2. In the left-side navigation pane, choose **Versions > Products**. The **Products** page appears.

3. On the Products page, click the  icon in the **Actions** column corresponding to the product information about which is to be modified.
4. In the dialog box that appears, modify the product name or description, and click **Submit**.

11.4.3.6 View information about product versions

When you need to learn about how to use a product, you can view information about the product version and API version.



Procedure

1. [Log on to the Apsara Opsapi Management system](#).
2. In the left-side navigation pane, choose **Versions > Products**. The **Products** page appears.
3. On the Products page, click the  icon in the **Actions** column corresponding to the product about which the version information is to be viewed.
You can view information about the product version and API version.

11.4.3.7 Modify information about product versions

You can modify information about a product version or API version as needed.

Procedure



1. [Log on to the Apsara Opsapi Management system](#).
2. In the left-side navigation pane, choose **Versions > Products**. The **Products** page appears.
3. On the **Products** page, click the  icon in the **Actions** column corresponding to the product about which the version information is to be modified.
4. In the **View Version** dialog box that appears, click the  icon in the **Actions** column corresponding to the version information about which is to be modified.
5. In the dialog box that appears, modify information about the product version and API version.

11.4.3.8 Remove information about product versions

You can remove information about a product version that is not applicable.

Procedure


1. [Log on to the Apsara Opsapi Management system](#).

2. In the left-side navigation pane, choose **Versions > Products**. The **Products** page appears.
3. On the **Products** page, click the  icon in the **Actions** column corresponding to the product about which the version information is to be removed.
4. In the **View Version** dialog box that appears, click the  icon in the **Actions** column corresponding to the version information about which is to be removed.
5. In the message that appears, click **OK**.

11.4.3.9 Remove information about products

You can remove information about a product that you no longer need.



Procedure

1. [Log on to the Apsara Opsapi Management system.](#)
2. In the left-side navigation pane, choose **Versions > Products**. The **Products** page appears.
3. Click the  icon in the **Actions** column corresponding to the product information about which is to be removed.

11.4.3.10 Remove information about product APIs

You can remove information about APIs that are not applicable to a product.

Procedure

1. [Log on to the Apsara Opsapi Management system.](#)
2. In the left-side navigation pane, choose **Versions > Products**. The **Products** page appears.
3. In the product list, click the  icon in the **Actions** column corresponding to the product to be managed.
4. In the dialog box that appears, select the product version from the left drop-down list.
Imported APIs are displayed in the APIs section.
5. Click the  icon corresponding to the API information about which is to be removed.
6. In the message that appears, click **Yes**.

11.4.4 SDK management

The Apsara Opsapi Management system enables you to customize SDKs. You can customize an SDK as needed to export APIs of Apsara Stack products of a specific version. You can also modify and delete the customized SDK.

11.4.4.1 Customize SDKs

The Apsara Opsapi Management system provides a tool to customize SDKs. The tool enables you to customize multiple combinations of SDKs for APIs within and across Apsara Stack products of specified versions.

Context

Each product has corresponding SDKs for different programming languages. The Apsara Opsapi Management system supports only SDKs for Java and Python.

Each SDK consists of an SDK core and an SDK model. The SDK core is the framework of the SDK. It is used to generate HTTP requests or requests of other protocols. The SDK core is fixed. You do not need to generate it each time. The SDK model defines the request parameters and responses of each API.

Procedure



1. [Log on to the Apsara Opsapi Management system.](#)
2. In the left-side navigation pane, choose **Versions > SDK Tools**. The **SDK Tools** page appears.
3. In the upper-right corner of the page, click **Customize SDK**.
4. Set Apsara Stack Version, Product Name, Product Version, SDK Version, API Version, and Language.

The corresponding APIs are displayed in the following APIs section.

5. Select APIs and click **Create SDK**.

After an SDK is created, you can view the created SDK in the SDK list on the **SDK Tools** page.

6. Optional: Click the link in the **Download** column corresponding to the product to download the SDK.

Customize SDK					
Product Name	Language	Apsara Stack Version	Generated At	Download	Actions
Drds	Java	v3.4	Jun 1, 2020, 10:03:26	drds-java-sdk_2020-06-01_100315.zip	 




Note:

The SDK generated in the Apsara Opsapi Management system is the SDK model. To use this SDK, you need to download the SDK core. You can download the SDK core from the Alibaba Cloud official website or obtain the SDK core from the Apsara Stack after-sales service.

11.4.4.2 Modify SDKs

When you need to update an SDK, you can upload an SDK to replace the original SDK.


Procedure

1. Log on to the [Apsara Opsapi Management system](#).
2. In the left-side navigation pane, choose **Versions > SDK Tools**. The **SDK Tools** page appears.
3. In the product list, click the  icon in the **Actions** column corresponding to the product of which the SDK is to be modified.
4. In the dialog box that appears, upload an SDK as prompted and click **Submit**.

Edit SDK:drds-java-sdk_2020-06-01_100315
✕

SDK Version:

Re-upload SDK:




Click or drag the file to this area to upload the file.

11.4.4.3 Delete SDKs

You can delete an SDK that you no longer need.

Procedure

1. [Log on to the Apsara Opsapi Management system.](#)
2. In the left-side navigation pane, choose **Versions > SDK Tools**. The **SDK Tools** page appears.
3. In the product list, click the  icon in the **Actions** column corresponding to the product of which the SDK is to be deleted.
4. In the message that appears, click **Yes**.

11.5 Test management

To facilitate API tests in the Apsara Opsapi Management system, the system provides the test management function. Each API can be saved as a test case during the test. A test case contains the request parameters of these APIs. You can associate multiple test cases to create a test set. You can choose to run one test case and one test set at a time. You can view execution results on the Execution History page.


11.5.1 Test cases

A test case is used to test a specified API.

11.5.1.1 Modify test cases

You can modify the request parameters of a test case as needed.

Procedure

1. [Log on to the Apsara Opsapi Management system.](#)
2. In the left-side navigation pane, choose **Testing Platform > Test Cases**. The **Test Cases** page appears.
3. On the Test Cases page, click the  icon in the **Actions** column corresponding to a test case.

4. In the Edit Test Case dialog box that appears, modify values of the regionId, accessKeyId, accessKeySecret, Product, apild, and apiVersion parameters.

Test Case Name: ListWorkBenchComponen

Request Parameters

regionId: cn

accessKeyId: [redacted]

accessKeySecret: [redacted]

product: ascm

apild: 15741

apiName: ListWorkBenchCompo

apiVersion: 2019-05-10

Save


5. Click **Save**.

11.5.1.2 Run test cases

You can run a test case as needed.

Procedure

1. [Log on to the Apsara Opsapi Management system](#).
2. In the left-side navigation pane, choose **Testing Platform > Test Cases**. The **Test Cases** page appears.


3. On the Test Cases page, click the  icon in the **Actions** column corresponding to a test case.

After the test case is run, you can choose **Testing Platform** > **Execution History** to view the execution results on the Execution History page.

11.5.1.3 Delete test cases

You can delete a test case that you no longer need.

Procedure

1. [Log on to the Apsara Opsapi Management system.](#)
2. In the left-side navigation pane, choose **Testing Platform** > **Test Cases**. The **Test Cases** page appears.
3. On the Test Cases page, click the  icon in the **Actions** column corresponding to the test case to be deleted.
4. In the message that appears, click **Yes**.

11.5.2 Test sets

A test set consists of multiple associated test cases.

11.5.2.1 Create test sets

You can create a test set based on test requirements.

Procedure

1. [Log on to the Apsara Opsapi Management system.](#)
2. In the left-side navigation pane, choose **Testing Platform** > **Test Sets**. The **Test Sets** page appears.
3. On the Test Sets page, click **Create Test Set**.
4. In the dialog box that appears, enter the test set name and description. Click **Save**.


We recommend that you enter a test set name that is easily identified.

11.5.2.2 Associate test cases

You can associate test cases with a test set to manage test cases in a unified manner.

Procedure

1. [Log on to the Apsara Opsapi Management system.](#)
2. In the left-side navigation pane, choose **Testing Platform** > **Test Sets**. The **Test Sets** page appears.




3. On the Test Sets page, click the  icon in the **Actions** column corresponding to the test set.
4. Optional: You can update the name and description of the test set and click **Save**.
5. Click **Relate to Test Case**.
6. In the dialog box that appears, search for and select the test case to be associated.
You can select multiple test cases and add them to the test set.
7. Click **Save**.


11.5.2.3 Run test sets

You can run a test set to check whether the APIs in the test set are available.

Procedure

1. [Log on to the Apsara Opsapi Management system](#).
2. In the left-side navigation pane, choose **Testing Platform** > **Test Sets**. The **Test Sets** page appears.


+ Create Test Set			
ID	Name	Description	Actions
1	osstestcase	test	  

3. On the Test Sets page, click the  icon in the **Actions** column corresponding to a test set.
The test cases in the test set start to run.
After the test set is run, you can choose **Testing Platform** > **Execution History** to view the execution results on the Execution History page.

11.5.2.4 Delete test sets

You can delete test sets that you no longer need.

Procedure

1. [Log on to the Apsara Opsapi Management system](#).
2. In the left-side navigation pane, choose **Testing Platform** > **Test Sets**. The **Test Sets** page appears.
3. On the Test Sets page, click the  icon in the **Actions** column corresponding to the test case to be deleted.
4. In the message that appears, click **Yes**.

11.5.3 View execution history of test cases

You can view information about the API for which a test case was executed, including the corresponding product, version information, execution time, and execution status.

Procedure

1. [Log on to the Apsara Opsapi Management system.](#)
2. In the left-side navigation pane, choose **Testing Platform > Execution History**. The **Execution History** page appears.
3. On the Execution History page, click the details icon in the **Details** column corresponding to the API to be viewed.
4. In the **Execution Details** dialog box that appears, view the execution details of the test case, including request parameters and responses.

11.6 System management

11.6.1 Metadatabase management

You can add or remove information about metadatabase in the Apsara Opsapi Management system.

11.6.1.1 View information about added metadatabases

The Apsara Opsapi Management system automatically scans all metadatabases in the Apsara Stack environment during initialization. The Apsara Opsapi Management system allows you to scan all metadatabases to view information about the added metadatabases. You can also manually add information about the metadatabases.

Context

The metadatabase information contains the domain name, database name, port, and server that are used in Apsara Stack products.

Procedure

1. [Log on to the Apsara Opsapi Management system.](#)
2. In the left-side navigation pane, choose **System Management > Metabase**. The **Metabase** page appears.


3. Use one of the following methods to view the connection information about metadatabases:

- Scan metadatabases

Click **Scan Metabase** to scan all added metadatabases in the Aspara Stack environment.

- Add information about metadatabases

Click **Add Metabase**. In the **Add Metabase** dialog box that appears, set Product Name, Metabase Name, Metabase Server, Metabase Port, Username, and Password. Click **Submit**.




Parameter	Description
Product Name	The product to which the metadatabase belongs.
MetaBase Name	The name of the metadatabase.
MetaBase Server	The name of the server where the metadatabase is located.
MetaBase Port	The access port of the metadatabase.
Username	The username used to log on to the metadatabase.
Password	The password used to log on to the metadatabase.







You can view information about the added metadatabases in the metadatabase list.

11.6.1.2 View connection information about metadatabases

You can view connection information about a metadatabase on the **Metabase** page.

Procedure


1. [Log on to the Apsara Opsapi Management system.](#)
2. In the left-side navigation pane, choose **System Management** > **Metabase**. The **Metabase** page appears.
3. In the upper-left corner of the page, select the product to view from the drop-down list.
4. On the Metabase page, click the  icon in the **Actions** column corresponding to a metadatabase. In the message that appears, you can view the metadatabase connection information.

Select a product. ▾		Scan Metabase Add Metabase		
Product	Database Name	Server Name	Port	Actions
oss	oss_chiji	oss- 	3896	
oss	oss_chiji_slave	oss- 	3896	
oss	mns_user_db	mns- 	3898	

11.6.1.3 Remove information about metadatabases

To facilitate management, you can remove information about metadatabases that you no longer need.

Procedure

1. [Log on to the Apsara Opsapi Management system.](#)
2. In the left-side navigation pane, choose **System Management** > **Metabase**. The **Metabase** page appears.
3. On the Metabase page, click the  icon in the **Actions** column corresponding to the metadatabase information about which is to be removed.
4. In the message that appears, click **Yes**.

11.6.2 Server management

You can add or remove information about servers in the Apsara Opsapi Management system.

11.6.2.1 View information about added servers

The Apsara Opsapi Management system automatically scans all servers (including physical servers and VMs) in the Apsara Stack environment during initialization. When new servers are added to the Apsara Stack environment, you can scan servers to view information about the added servers. You can also add information about the added servers.

Procedure

1. [Log on to the Apsara Opsapi Management system.](#)
2. In the left-side navigation pane, choose **System Management** > **Server Management**.
The **Server Management** page appears.

3. Use either of the following methods to view information about added servers:

- Scan servers

Click **Scan Server** to scan the information about all servers in the Apsara Stack environment.

- Add information about new servers

Click **Add Server**. In the **Add Server** dialog box that appears, set Name, Server Name, Server IP, SSH Port, and SSH User. Upload the SSH private key. Click **Submit**.

The screenshot shows a web-based dialog box titled "Add Server". It contains the following fields and controls:

- * Name:** A text input field with the placeholder text "Alias. Typically it's the pr...".
- * Server Name:** A text input field with the placeholder text "Server Name".
- * Server IP:** A text input field with the placeholder text "IP Address".
- * SSH Port:** A text input field with the placeholder text "Port".
- * SSH User:** A text input field with the placeholder text "SSH User".
- SSH Password:** A text input field with the placeholder text "SSH Password".
- SSH Private Key:** A text input field followed by a button labeled "Upload SSH Private Key".
- Submit:** A blue button at the bottom center of the dialog.


You can view information about the added servers in the server list.

11.6.2.2 Remove server information

To facilitate management, you can remove information about servers that you no longer need.

Procedure


1. [Log on to the Apsara Opsapi Management system.](#)

2. In the left-side navigation pane, choose **System Management > Server Management**.
The **Server Management** page appears.
3. On the Server Management page, click the  icon in the **Actions** column corresponding to the server information about which is to be removed.

11.6.3 Audit APIs

You can view call records of all Opsapis. The records contain the specific API, statuses, time, and result of each call.

Procedure

1. [Log on to the Apsara Opsapi Management system](#).
2. In the left-side navigation pane, choose **System Management > API Audit**. The **API Audit** page appears.
3. On the API Audit page, click the  icon in the **Actions** column corresponding to the API.
You can view the call result of this API.

11.6.4 View logs

You can view API logs, error logs, and Egg logs to better maintain the back end.

Procedure

1. [Log on to the Apsara Opsapi Management system](#).
2. In the left-side navigation pane, choose **System Management > Log Management**. The **Log Management** page appears.

3. View the details of all logs on the **API Log**, **Error Log**, and **Egg Log** tabs.



The screenshot shows the Apsara Opsapi Management system log viewer. The 'API Log' tab is selected, and the 'Log Level' dropdown is set to 'info'. The log entries are as follows:

```

1 2019-06-06 00:00:50,119 INFO 49 loading all APIs .....
2 2019-06-06 00:00:50,289 INFO 55 loading all APIs .....
3 2019-06-06 00:00:54,431 INFO 49 loading all APIs .....
4 2019-06-06 00:00:55,871 INFO 61 loading all APIs .....
5 2019-06-06 00:01:17,630 INFO 55 loading all APIs .....
6 2019-06-06 00:01:17,613 INFO 61 loading all APIs .....
7 2019-06-06 00:01:17,655 ERROR 61 Failed to fetch pangu data from pangu API: { Error: connect ECONNREFUSED 10.16.20.8:8620
8   at Object._errnoException (util.js:1022:11)
9   at _exceptionWithHostPort (util.js:1044:20)
10  at TCPConnectWrap.afterConnect [as oncomplete] (net.js:1182:14)
11  code: 'ECONNREFUSED',
12  errno: 'ECONNREFUSED',
13  syscall: 'connect',
14  address: '10.16.20.8',
15  port: 8620,
16  source: 'API Server' }
17 2019-06-06 00:01:17,635 INFO 48 loading all APIs .....
18 2019-06-06 00:01:17,675 INFO 48 loading all APIs .....
19 2019-06-06 00:01:17,630 INFO 49 loading all APIs .....
20 2019-06-06 00:01:17,705 ERROR 49 { Code: 'ResourceNotExist',
21  Message: 'serviceInstance does not exist',
22  status: 404 }
23 2019-06-06 00:03:37,178 INFO 49 loading all APIs .....
24 2019-06-06 00:03:37,337 INFO 55 loading all APIs .....
25 2019-06-06 00:03:40,512 INFO 49 loading all APIs .....
26 2019-06-06 00:04:36,555 ERROR 49 { Code: 'ResourceNotExist',
27  Message: 'serviceInstance does not exist',
28  status: 404 }
29 2019-06-06 00:04:36,588 ERROR 55 { Code: 'ResourceNotExist',
30  Message: 'serviceInstance does not exist',
31  status: 404 }
32 2019-06-06 00:04:36,565 ERROR 61 { Code: 'ResourceNotExist',
33  Message: 'serviceInstance does not exist',
34  status: 404 }
35 2019-06-06 00:04:36,567 ERROR 49 { Code: 'ResourceNotExist',
36  Message: 'serviceInstance does not exist',
37  status: 404 }

```



Note:

You can modify log levels in the Apsara Opsapi Management system in real time. The level you set is valid only during the active service operating period. If you restart the service, the default level remains.

12 Appendix

12.1 Operation Access Manager (OAM)

12.1.1 OAM introduction

Overview


Operation Access Manager (OAM) is a centralized permission management platform of Apsara Stack Operations (ASO). OAM uses a simplified role-based access control (RBAC) model. Administrators can use OAM to assign roles to operations personnel, granting them corresponding operation permissions to operations systems.

OAM permission model

In RBAC, administrators do not directly grant system operation permissions to users. Instead, they create a collection of roles between a collection of users and a collection of permissions. Each role corresponds to a group of permissions. If a role is assigned to a user, the user is granted all the operation permissions of that role. Therefore, when creating a user, administrators are only required to assign a role to the user, saving the trouble to grant specific permissions to the user. In addition, the frequency of role permission changes is less than that of user permission changes, simplifying the user permission management and reducing the system overhead.

See the [OAM permission model](#) as follows.

Figure 12-1: Permission model



12.1.2 Instructions

Before using Operation Access Manager (OAM), you must know the following basic concepts about permission management.

subject

Operators of the access control system. OAM has two types of subjects: users and groups.

user

Administrators and operators of operations systems.

group

A collection of users.

role

The core of the role-based access control (RBAC) system.

Generally, a role can be regarded as a collection of permissions. A role can contain multiple RoleCells or roles.

RoleHierarchy

In the OAM system, a role can contain other roles to form RoleHierarchy.

RoleCell

The specific description of a permission. A RoleCell consists of resources, ActionSets, and available authorizations.

resource

The description of an authorized object. For more information about resources of operations platforms, see [Permission lists of operations platforms](#).

ActionSet

The description of authorized actions. An ActionSet can contain multiple actions. For more information about actions of operations platforms, see [Permission lists of operations platforms](#).

available authorizations

The maximum number of authorizations in the cascaded authorization, which is an integer greater than or equal to zero. If the value is not zero, the permission can be granted. If the value is zero, the permission cannot be granted.

For example, if administrator A sets **Available Authorizations** to 5 when granting a permission to administrator B, the permission can be granted for another five times at most. When administrator B grants the permission to administrator C, the value of **Available Authorizations** cannot be greater than 4. If **Available Authorizations** is set to 0 when administrator B grants the permission to operator D, operator D can only use the permission but cannot grant it to others.

**Note:**

Currently, OAM does not support the cascaded revocation for cascaded authorization. Therefore, administrator C and operator D still have the permission even if the permission is revoked for administrator B.

12.1.3 Quick start

This topic describes how to add and assign roles quickly.

12.1.3.1 Log on to OAM

This topic describes how to log on to Operation Access Manager (OAM).


Prerequisites

- ASO access address in the format of `http://region-id.aso.intranet-domain-id.com`.

- Google Chrome browser (recommended).

Procedure

1. Open the browser.
2. Enter the ASO access address `http://region-id.aso.intranet-domain-id.com` in the address bar and then press Enter.

A screenshot of the ASO Log On interface. It features a dark blue background with the text 'Log On' in white at the top left. Below this, there are two input fields: the first is preceded by a user icon and the placeholder text 'Enter a user name'; the second is preceded by a lock icon and the placeholder text 'Enter the password'. At the bottom, there is a prominent blue button with the text 'Log On' in white.**Note:**

You can select the language from the drop-down list in the upper-right corner to change the language of ASO.

3. Enter the correct username and password.

**Note:**

Obtain the username and password used to log on to ASO from the deployment personnel or the administrator.

- The system has three default users:
 - Security officer: manages other users or roles.
 - Auditor officer: views audit logs.
 - System administrator: used for other functions except those of the security officer and auditor officer.
- You must modify the password of your username as instructed when you log on to ASO for the first time. To improve security, the password must be 10-20 characters long and can contain English uppercase/lowercase letters (A-Z or a-z), numbers (0-

9), and special characters, such as exclamation points (!), at signs (@), number signs (#), dollar signs (\$), and percent signs (%), which meets the minimum complexity requirements.

4. Click **Log On** to log on to ASO.
5. In the left-side navigation pane, select **Products**.
6. Click **OAM** under **Apsara Stack O&M**.

12.1.3.2 Create a group

Create a user group for centralized management.

Procedure

1. [Log on to OAM](#).
2. In the left-side navigation pane, choose **Group Management > Owned Groups**.
3. In the upper-right corner, click **Create Group**. In the displayed dialog box, enter the **Group Name** and **Description**.
4. Then, click **Confirm**.

You can view the created group on the **Owned Groups** page.

12.1.3.3 Add group members

Add members to an existing group to grant permissions to the group members in a centralized way.

Procedure

1. [Log on to OAM](#).
2. In the left-side navigation pane, choose **Group Management > Owned Groups**.
3. Find the group and then click **Manage** in the **Actions** column.
4. Click **Add Member** in the **Group Member** section.

5. Select the search mode, enter the corresponding information, and then click **Details**. The user details are displayed.

Three search modes are available:

- **RAM User Account:** Search for the user in the format of RAM username@primary account ID.
- **Account Primary Key:** Search for the user by using the unique ID of the user's cloud account.
- **Logon Account Name:** Search for the user by using the logon name of the user's cloud account.

6. Click **Add**.

7. You can repeat the preceding steps to add more group members.

To remove a member from the group, click **Remove** in the **Actions** column at the right of the member.

12.1.3.4 Add group roles

You can add roles to an existing group, that is, assign roles to the group.

Prerequisites

- The role to be added is created. For more information about how to create a role, see [Create a role](#).
- You are the owner of the group and the role.

Procedure

1. [Log on to OAM](#).
2. In the left-side navigation pane, choose **Group Management > Owned Groups**.
3. Find the group and then click **Manage** in the **Actions** column.
4. Click **Add Role** in the **Role List** section.
5. Search for roles by **Role Name**. Select one or more roles and then configure the expiration time.
6. Then, click **Confirm**.

To remove a role from the group, click **Remove** in the **Actions** column at the right of the role in the **Role List** section.

12.1.3.5 Create a role

Procedure

1. [Log on to OAM.](#)
2. In the left-side navigation pane, choose **Role Management > Owned Roles**.
3. In the upper-right corner of the **Owned Roles** page, click **Create Role**.
4. In the displayed dialog box, enter the **Role Name** and **Description**, and then select the **Role Type**.
5. Optional: Configure the role tags, which can be used to filter roles.
 - a) Click **Edit Tag**.
 - b) In the displayed **Edit Tags** dialog box, click **Create**.
 - c) Enter the **Key** and the corresponding **Value** of the tag and then click **Confirm**.
 - d) Repeat the preceding step to create more tags.

The created tags are displayed in the dotted box.
 - e) Click **Confirm** to create the tags.
6. Click **Confirm** to create the role.

12.1.3.6 Add inherited roles to a role

Add inherited roles to a role to grant the permissions of the former to the latter.

Prerequisites

You are the owner of the current role and the inherited role to be added.

For more information about how to search for your owned roles, see [Search for roles](#).

Procedure

1. [Log on to OAM.](#)
2. In the left-side navigation pane, choose **Role Management > Owned Roles**.
3. Find the role and then click **Manage** in the **Actions** column.
4. Click the **Inherited Role** tab.
5. Click **Add Role**. Search for roles by **Role Name** and then select one or more roles.
6. Click **Confirm**.

12.1.3.7 Add resources to a role


You must add resources to a created role.

Procedure

1. [Log on to OAM.](#)
2. In the left-side navigation pane, choose **Role Management > Owned Roles**.

3. Find the role and then click **Manage** in the **Actions** column.
4. Click the **Resource List** tab.
5. Click **Add Resource**.
6. Complete the configurations. For more information, see [Table 12-1: Configurations](#).

Table 12-1: Configurations

Configuration item	Description
BID	The deployment region ID.
Product	<p>The cloud product to be added, for example, rds.</p> <div>  Note: The cloud product name must be lowercase. For example, enter rds, instead of RDS. </div>
Resource Path	For more information about resources of cloud products and operations platforms, see Permission lists of operations platforms .
Actions	<p>An ActionSet, which can contain multiple actions.</p> <p>For more information about actions of operations platforms, see Permission lists of operations platforms.</p>
Available Authorizations	The maximum number of authorizations in the cascaded authorization, which is an integer greater than or equal to zero. If the value is not zero, the permission can be granted. If the value is zero, the permission cannot be granted.
Description	The description of the resource.

7. Click **Add**.

12.1.3.8 Add authorized users to a role

You can assign an existing role to users or user groups.

Prerequisites

The corresponding users or user groups are created. Users are created in the Apsara Stack console. For more information about how to create user groups, see [Create a group](#).

Procedure

1. [Log on to OAM](#).
2. In the left-side navigation pane, choose **Role Management** > **Owned Roles**.

3. Find the role and then click **Manage** in the **Actions** column.
4. Click the **Authorized Users** tab.
5. Click **Add User**.
6. Select the search mode and enter the corresponding information.

Four search modes are available:

- **RAM User Account:** search in the format of RAM username@primary account ID.
- **Account Primary Key:** search by using the unique ID of the user's cloud account.
- **Logon Account Name:** search by using the logon name of the user's cloud account.
- **Group Name:** search by group name.



Note:

You can search for a single user or user group. For more information about how to create a user group, see [Create a group](#).

7. Configure the expiration time.

After the expiration time is reached, the user does not have the permissions of the role. To authorize the user again, the role creator must click **Renew** at the right of the authorized user on the **Authorized Users** tab, and then configure the new expiration time.

8. Click **Add** to assign the role to the user.

To cancel the authorization, click **Remove** at the right of the authorized user on the **Authorized Users** tab.

12.1.4 Manage groups

Group Management allows you to view, modify, or delete groups.

12.1.4.1 Modify the group information

After creating a group, you can modify the group name and description on the **Group Information** page.

Procedure

1. [Log on to OAM](#).
2. In the left-side navigation pane, choose **Group Management** > **Owned Groups**.
3. Find the group and then click **Manage** in the **Actions** column.
4. Click **Modify** in the upper-right corner.

5. In the displayed **Modify Group** dialog box, modify the **Group Name** and **Description**.
6. Click **Confirm**.

12.1.4.2 View group role details

You can view the information about the inherited roles, resource list, and inheritance tree of a group role.

Prerequisites

A role is added to the group.

Procedure

1. [Log on to OAM](#).
2. In the left-side navigation pane, choose **Group Management > Owned Groups**.
3. Find the group and then click **Manage** in the **Actions** column.
4. In the **Role List** section, click **Details** at the right of a role.
5. On the **Role Information** page, you can:
 - Click the **Inherited Role** tab to view the information about the inherited roles.

To view the detailed information of an inherited role, click **Details** in the **Actions** column at the right of the inherited role.
 - Click the **Resource List** tab to view the resource information of the role.

To add other resources to this role, see [Add resources to a role](#).
 - Click the **Inheritance Tree** tab to view the basic information and resource information of the role and its inherited roles by using the inheritance tree on the left.

12.1.4.3 Delete a group

You can delete a group that is no longer in use as required.

Prerequisites

The group to be deleted does not contain members.

Procedure

1. [Log on to OAM](#).
2. In the left-side navigation pane, choose **Group Management > Owned Groups**.
3. Find the group to be deleted and then click **Delete** in the **Actions** column.

12.1.4.4 View authorized groups

You can view the groups to which you are added on the **Authorized Groups** page.

Context

You can only view the groups to which you belong, but cannot view groups of other users.

Procedure

1. [Log on to OAM](#).
2. In the left-side navigation pane, choose **Group Management > Authorized Groups**.
3. On the **Authorized Groups** page, view the name, owner, description, and modified time of the group to which you belong.

12.1.5 Manage roles

Role Management allows you to view, modify, transfer, or delete roles.

12.1.5.1 Search for roles

You can view your owned roles on the **Owned Roles** page.

Procedure

1. [Log on to OAM](#).
2. In the left-side navigation pane, choose **Role Management > Owned Roles**.
3. Optional: Enter the role name.
4. Click **Search** to search for roles that meet the search condition.



Note:

If the role you want to search for has a tag, you can click **Tag** and select the tag key to search for the role based on the tag.

12.1.5.2 Modify the role information

After creating a role, you can modify the role information.

Procedure

1. [Log on to OAM](#).
2. In the left-side navigation pane, choose **Role Management > Owned Roles**.
3. Find the role and then click **Manage** in the **Actions** column.
4. Click **Modify** in the upper-right corner.
5. In the displayed **Modify Role** dialog box, modify the **Role Name**, **Description**, **Role Type**, and **Tag**.

6. Then, click **Confirm**.

12.1.5.3 View the role inheritance tree

You can view the role inheritance tree to know the basic information and resource information of a role and its inherited roles.

Procedure

1. [Log on to OAM](#).
2. In the left-side navigation pane, choose **Role Management > Owned Roles**.
3. Find the role and then click **Manage** in the **Actions** column.
4. Click the **Inheritance Tree** tab.

View the basic information and resource information of this role and its inherited roles by using the inheritance tree on the left.

12.1.5.4 Transfer roles

You can transfer roles to other groups or users according to business requirements.

Procedure

1. [Log on to OAM](#).
2. In the left-side navigation pane, choose **Role Management > Owned Roles**.
3. Configure the search condition and search for the roles to be transferred.
4. Select one or more roles in the search results and click **Transfer**.
5. In the displayed **Transfer** dialog box, select the search mode, enter the corresponding information, and then click **Details**. The user details or group details are displayed.

Four search modes are available:

- **RAM User Account:** search in the format of RAM username@primary account ID.
 - **Account Primary Key:** search by using the unique ID of the user's cloud account.
 - **Logon Account Name:** search by using the logon name of the user's cloud account.
 - **Group Name:** search by group name.
6. Click **Transfer** to transfer the roles to the user or group.

12.1.5.5 Delete a role

You can delete a role that is no longer in use according to business requirements.

Prerequisites

The role to be deleted does not contain inherited roles, resources, or authorized users.

Procedure

1. [Log on to OAM.](#)
2. In the left-side navigation pane, choose **Role Management > Owned Roles**.
3. At the right of the role to be deleted and then click **Delete**.

12.1.5.6 View authorized roles

You can view the roles assigned to you and permissions granted to the roles.

Procedure

1. [Log on to OAM.](#)
2. In the left-side navigation pane, choose **Role Management > Authorized Roles**.
3. On the **Authorized Roles** page, you can view the name, owner, description, modified time, and expiration time of the role assigned to you.

Click **Details** at the right of a role to view the inherited roles, resources, and inheritance tree information of the role.

12.1.5.7 View all roles

You can view all the roles in Operation Access Manager (OAM) on the **All Roles** page.

Procedure

1. [Log on to OAM.](#)
2. In the left-side navigation pane, choose **Role Management > All Roles**.
3. On the **All Roles** page, view all the roles in the system.

You can search for roles by **Role Name** on this page.
4. At the right of a role, click **Details** to view the inherited roles, resources, and inheritance tree information of the role.

12.1.6 Search for resources

You can search for resources to view the roles to which the resources are assigned.

Procedure

1. [Log on to OAM.](#)
2. In the left-side navigation pane, select **Search Resource**.
3. Enter the **Resource** and **Action** in the search boxes, and then click **Search** to search for roles that meet the conditions.

4. At the right of a role, click **Details** in the **Actions** column to view the inherited roles, resources, and inheritance tree information of the role.

12.1.7 View the personal information

You can view the personal information of the current user and test the permissions on the **Personal Information** page.

Procedure

1. [Log on to OAM](#).
2. In the left-side navigation pane, select **Personal Information**.
3. In the **Basic Information** section, you can view the username, user type, created time, AccessKey ID, and AccessKey Secret of the current user.

**Note:**

Click **Show** or **Hide** to show or hide the AccessKey Secret.

4. In the **Test Permission** section, test if the current user has a certain permission.
 - a) Enter the resource information in the **Resource** field.

**Note:**

Use the English input method when entering values in the **Resource** and **Action** fields.

- b) Enter the permissions in the **Action** field, such as create, read, and write. Separate multiple permissions with commas (,).

12.1.8 Appendix

12.1.8.1 Default roles and their functions

This topic describes the default roles in Operation Access Manager (OAM) and their functions.

12.1.8.1.1 Default role of OAM

This topic describes the default role of Operation Access Manager (OAM) and the corresponding available authorizations.

Role name	Role description	Resource	Actions	Available authorizations
Super administrator	An administrator with root permissions	*.*	*	10

12.1.8.1.2 Default roles of Apsara Infrastructure Management Framework

This topic describes the default roles of Apsara Infrastructure Management Framework and the corresponding available authorizations.

Role name	Role description	Resource	Actions	Available authorizations
Tianji_Project read-only	Has the read-only permission to Apsara Infrastructure Management Framework projects, which allows you to view the configurations and statuses of all projects and clusters	*:tianji:projects	["read"]	0

Role name	Role description	Resource	Actions	Available authorizations
Tianji_Project administrator	Has all the permissions to Apsara Infrastructure Management Framework projects, which allows you to view and modify the configurations and statuses of all projects and clusters	*:tianji:projects	["*"]	0
Tianji_Service read-only	Has the read-only permission to Apsara Infrastructure Management Framework services, which allows you to view the configurations and templates of all services	*:tianji:services	["read"]	0
Tianji_Service administrator	Has all the permissions to Apsara Infrastructure Management Framework services, which allows you to view and modify the configurations and templates of all services	*:tianji:services	["*"]	0

Role name	Role description	Resource	Actions	Available authorizations
Tianji_IDC administrator	Has all the permissions to Apsara Infrastructure Management Framework data centers, which allows you to view and modify the data center information	*:tianji:idcs	["*"]	0
Tianji administrator	Has all the permissions to Apsara Infrastructure Management Framework, which allows you to perform operations on all Apsara Infrastructure Management Framework configurations	*:tianji	["*"]	0

12.1.8.1.3 Default role of Tianjimon

This topic describes the default role of Tianjimon and the corresponding available authorizations.

Role name	Role description	Resource	Actions	Available authorizations
Tianjimon operations	Has all Tianjimon permissions, which allows you to perform basic monitoring and operations	26842:tianjimon:*	["*"]	0

12.1.8.2 Permission lists of operations platforms

This topic describes the permissions of operations platforms.

12.1.8.2.1 Permission list of Apsara Infrastructure Management Framework

This topic describes the permissions of Apsara Infrastructure Management Framework.

Resource	Action	Description
*:tianji:services:[sname]: tjmontemplates:[tplname]	delete	DeleteServiceTjmonTpl
*:tianji:services:[sname]: tjmontemplates:[tplname]	write	PutServiceTjmonTpl
*:tianji:services:[sname]: templates:[tplname]	write	PutServiceConfTpl
*:tianji:services:[sname]: templates:[tplname]	delete	DeleteServiceConfTpl
*:tianji:services:[sname]: serviceinstances:[sname]: tjmontemplate	read	GetServiceInstanceTjmonTpl
*:tianji:services:[sname]: serviceinstances:[sname]: tssessions	terminal	CreateTsSessionByService
*:tianji:services:[sname]: serviceinstances:[sname]: template	write	SetServiceInstanceTpl
*:tianji:services:[sname]: serviceinstances:[sname]: template	delete	DeleteServiceInstanceTpl
*:tianji:services:[sname]: serviceinstances:[sname]: template	read	GetServiceInstanceTpl
*:tianji:services:[sname]: serviceinstances:[sname]: tags:[tag]	delete	DeleteServiceInstanceProductTagInService
*:tianji:services:[sname]: serviceinstances:[sname]: tags:[tag]	write	AddServiceInstanceProductTagInService

Resource	Action	Description
*:tianji:services:[sname]:serviceinstances:[siname]:serverroles:[serverrole]:resources	read	GetServerroleResourceInService
*:tianji:services:[sname]:serviceinstances:[siname]:serverroles:[serverrole]:machines:[machine]	write	OperateSRMachineInService
*:tianji:services:[sname]:serviceinstances:[siname]:serverroles:[serverrole]:machines:[machine]	read	GetMachineSRInfoInService
*:tianji:services:[sname]:serviceinstances:[siname]:serverroles:[serverrole]:machines:[machine]	delete	DeleteSRMachineActionInService
*:tianji:services:[sname]:serviceinstances:[siname]:serverroles:[serverrole]:machines	read	GetMachinesSRInfoInService
*:tianji:services:[sname]:serviceinstances:[siname]:serverroles:[serverrole]:machines	delete	DeleteSRMachinesActionInService
*:tianji:services:[sname]:serviceinstances:[siname]:serverroles:[serverrole]:machines	write	OperateSRMachinesInService
*:tianji:services:[sname]:serviceinstances:[siname]:serverroles:[serverrole]:apps:[app]:resources	read	GetAppResourceInService
*:tianji:services:[sname]:serviceinstances:[siname]:serverroles:[serverrole]:apps:[app]:machines:[machine]:tianjilogs	read	TianjiLogsInService

Resource	Action	Description
*:tianji:services:[sname]:serviceinstances:[siname]:serverroles	read	GetServiceInstanceServerrolesInService
*:tianji:services:[sname]:serviceinstances:[siname]:schema	write	SetServiceInstanceSchema
*:tianji:services:[sname]:serviceinstances:[siname]:schema	delete	DeleteServiceInstanceSchema
*:tianji:services:[sname]:serviceinstances:[siname]:rollings:[version]	write	OperateRollingJobInService
*:tianji:services:[sname]:serviceinstances:[siname]:rollings	read	ListRollingJobInService
*:tianji:services:[sname]:serviceinstances:[siname]:resources	read	GetInstanceResourceInService
*:tianji:services:[sname]:serviceinstances:[siname]:machines:[machine]	read	GetMachineAllSRInfoInService
*:tianji:services:[sname]:serviceinstances:[siname]	write	DeployServiceInstanceInService
*:tianji:services:[sname]:serviceinstances:[siname]	read	GetServiceInstanceConf
*:tianji:services:[sname]:serverroles:[serverrole]:machines:[machine]:apps:[app]:files:name	read	GetMachineAppFileListInService
*:tianji:services:[sname]:serverroles:[serverrole]:machines:[machine]:apps:[app]:files:download	read	GetMachineAppFileDownloadInService
*:tianji:services:[sname]:serverroles:[serverrole]:machines:[machine]:apps:[app]:files:content	read	GetMachineAppFileContentInService

Resource	Action	Description
*:tianji:services:[sname]: serverroles:[serverrole]: machines:[machine]:apps:[app]:filelist	read	GetMachineFileListInService
*:tianji:services:[sname]: serverroles:[serverrole]: machines:[machine]:apps:[app]:dockerlogs	read	DockerLogsInService
*:tianji:services:[sname]: serverroles:[serverrole]: machines:[machine]:apps:[app]:debuglog	read	GetMachineDebugLogIn Service
*:tianji:services:[sname]: serverroles:[serverrole]: machines:[machine]:apps	read	GetMachineAppListInService
*:tianji:services:[sname]: serverroles:[serverrole]:apps :[app]:dockerinspect	read	DockerInspect
*:tianji:services:[sname]: schemas:[schemaname]	write	PutServiceSchema
*:tianji:services:[sname]: schemas:[schemaname]	delete	DeleteServiceSchema
*:tianji:services:[sname]: resources	read	GetResourceInService
*:tianji:services:[sname]	delete	DeleteService
*:tianji:services:[sname]	write	CreateService
*:tianji:projects:[pname]: machinebuckets:[bname]: machines:[machine]	read	GetMachineBucketMach ineInfo
*:tianji:projects:[pname]: machinebuckets:[bname]: machines	read	GetMachineBucketMachines
*:tianji:projects:[pname]: machinebuckets:[bname]	write	CreateMachineBucket
*:tianji:projects:[pname]: machinebuckets:[bname]	write	OperateMachineBucket Machines

Resource	Action	Description
*:tianji:projects:[pname]:machinebuckets:[bname]	delete	DeleteMachineBucket
*:tianji:projects:[pname]:machinebuckets:[bname]	read	GetMachineBucketMachinesLegacy
*:tianji:projects:[pname]:machinebuckets	read	GetMachineBucketList
*:tianji:projects:[pname]:projects:[pname]:clusters:[cname]:tsessions:[tsessionname]:tsses	terminal	UpdateTsSessionTssByCluster
*:tianji:projects:[pname]:projects:[pname]:clusters:[cname]:tsessions	terminal	CreateTsSessionByCluster
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[siname]:tjmontemplate	read	GetServiceInstanceTjmonTplInCluster
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[siname]:template	delete	DeleteServiceInstanceTplInCluster
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[siname]:template	write	SetServiceInstanceTplInCluster
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[siname]:template	read	GetServiceInstanceTplInCluster
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[siname]:tags:[tag]	write	AddServiceInstanceProductTagInCluster
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[siname]:tags:[tag]	delete	DeleteServiceInstanceProductTagInCluster
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[siname]:serverroles:[serverrole]:resources	read	GetServerroleResourceInCluster

Resource	Action	Description
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[sname]:serverroles:[serverrole]:machines:[machine]:apps:[app]:files:name	read	GetMachineAppFileList
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[sname]:serverroles:[serverrole]:machines:[machine]:apps:[app]:files:download	read	GetMachineAppFileDownload
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[sname]:serverroles:[serverrole]:machines:[machine]:apps:[app]:files:content	read	GetMachineAppFileContent
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[sname]:serverroles:[serverrole]:machines:[machine]:apps:[app]:filelist	read	GetMachineFileList
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[sname]:serverroles:[serverrole]:machines:[machine]:apps:[app]:dockerlogs	read	DockerLogsInCluster
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[sname]:serverroles:[serverrole]:machines:[machine]:apps:[app]:debuglog	read	GetMachineDebugLog
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[sname]:serverroles:[serverrole]:machines:[machine]:apps	read	GetMachineAppList

Resource	Action	Description
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[sname]:serverroles:[serverrole]:machines:[machine]	read	GetMachineSRInfoInCluster
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[sname]:serverroles:[serverrole]:machines:[machine]	write	OperateSRMachineInCluster
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[sname]:serverroles:[serverrole]:machines:[machine]	delete	DeleteSRMachineActionInCluster
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[sname]:serverroles:[serverrole]:machines	write	OperateSRMachinesInCluster
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[sname]:serverroles:[serverrole]:machines	delete	DeleteSRMachinesActionInCluster
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[sname]:serverroles:[serverrole]:machines	read	GetAllMachineSRInfoInCluster
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[sname]:serverroles:[serverrole]:apps:[app]:resources	read	GetAppResourceInCluster
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[sname]:serverroles:[serverrole]:apps:[app]:machines:[machine]:tianjilogs	read	TianjiLogsInCluster

Resource	Action	Description
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[siname]:serverroles:[serverrole]:apps:[app]:dockerinspect	read	DockerInspectInCluster
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[siname]:serverroles	read	GetServiceInstanceServerrolesInCluster
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[siname]:schema	delete	DeleteServiceInstanceSchemaInCluster
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[siname]:schema	write	SetServiceInstanceSchemaInCluster
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[siname]:resources	read	GetInstanceResourceInCluster
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[siname]	delete	DeleteServiceInstance
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[siname]	write	CreateServiceInstance
*:tianji:projects:[pname]:clusters:[cname]:serviceinstances:[siname]	read	GetServiceInstanceConfigInCluster
*:tianji:projects:[pname]:clusters:[cname]:rollings:[version]	write	OperateRollingJob
*:tianji:projects:[pname]:clusters:[cname]:rollings	read	ListRollingJob
*:tianji:projects:[pname]:clusters:[cname]:resources	read	GetResourceInCluster
*:tianji:projects:[pname]:clusters:[cname]:quota	write	SetClusterQuotas

Resource	Action	Description
*:tianji:projects:[pname]:clusters:[cname]:machinesinfo	read	GetClusterMachineInfo
*:tianji:projects:[pname]:clusters:[cname]:machines:[machine]	read	GetMachineAllSRInfo
*:tianji:projects:[pname]:clusters:[cname]:machines:[machine]	write	SetMachineAction
*:tianji:projects:[pname]:clusters:[cname]:machines:[machine]	delete	DeleteMachineAction
*:tianji:projects:[pname]:clusters:[cname]:machines	write	OperateClusterMachines
*:tianji:projects:[pname]:clusters:[cname]:difflist	read	GetVersionDiffList
*:tianji:projects:[pname]:clusters:[cname]:diff	read	GetVersionDiff
*:tianji:projects:[pname]:clusters:[cname]:deploylogs:[version]	read	GetDeployLogInCluster
*:tianji:projects:[pname]:clusters:[cname]:deploylogs	read	GetDeployLogListInCluster
*:tianji:projects:[pname]:clusters:[cname]:builds:[version]	read	GetBuildJob
*:tianji:projects:[pname]:clusters:[cname]:builds	read	ListBuildJob
*:tianji:projects:[pname]:clusters:[cname]	write	OperateCluster
*:tianji:projects:[pname]:clusters:[cname]	delete	DeleteCluster
*:tianji:projects:[pname]:clusters:[cname]	read	GetClusterConf
*:tianji:projects:[pname]:clusters:[cname]	write	DeployCluster

Resource	Action	Description
*:tianji:projects:[pname]	write	CreateProject
*:tianji:projects:[pname]	delete	DeleteProject
*:tianji:idcs:[idc]:rooms:[room]:racks:[rack]:rackunits:[rackunit]	write	CreateRackunit
*:tianji:idcs:[idc]:rooms:[room]:racks:[rack]:rackunits:[rackunit]	write	SetRackunitAttr
*:tianji:idcs:[idc]:rooms:[room]:racks:[rack]:rackunits:[rackunit]	delete	DeleteRackunit
*:tianji:idcs:[idc]:rooms:[room]:racks:[rack]	write	SetRackAttr
*:tianji:idcs:[idc]:rooms:[room]:racks:[rack]	write	CreateRack
*:tianji:idcs:[idc]:rooms:[room]:racks:[rack]	delete	DeleteRack
*:tianji:idcs:[idc]:rooms:[room]	write	CreateRoom
*:tianji:idcs:[idc]:rooms:[room]	delete	DeleteRoom
*:tianji:idcs:[idc]:rooms:[room]	write	SetRoomAttr
*:tianji:idcs:[idc]	delete	Deleteldc
*:tianji:idcs:[idc]	write	SetIdcAttr
*:tianji:idcs:[idc]	write	CreateIdc

12.1.8.2.2 Permission list of Tianjimon

This topic describes the permission of Tianjimon.

Resource	Action	Description
26842:tianjimon:monitor-manage	manage	Monitoring and operations